

Using the GNU Privacy Guard

Version 2.2.27
December 2020



The GnuPG Project (<https://gnupg.org>)

This is the *The GNU Privacy Guard Manual* (version 2.2.27, December 2020).

Published by The GnuPG Project

<https://gnupg.org>

(or <http://ic6au7wa3f6naxjq.onion>)

© 2002, 2004, 2005, 2006, 2007, 2010 Free Software Foundation, Inc.

© 2013, 2014, 2015 Werner Koch.

© 2015, 2016, 2017 g10 Code GmbH.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version. The text of the license can be found in the section entitled “Copying”.

Short Contents

1	A short installation guide.....	1
2	Invoking GPG-AGENT	3
3	Invoking DIRMNGR.....	23
4	Invoking GPG.....	35
5	Invoking GPGSM	97
6	Invoking the SCDAEMON.....	119
7	How to Specify a User Id	129
8	Trust Values	133
9	Helper Tools	135
10	Web Key Service.....	161
11	How to do certain things	167
12	Notes pertaining to certain OSes	173
13	How to solve problems	175
	GNU General Public License	181
	Contributors to GnuPG	193
	Glossary	195
	Option Index	197
	Environment Variable and File Index	203
	Index.....	205

Table of Contents

1	A short installation guide	1
2	Invoking GPG-AGENT	3
2.1	Commands.....	3
2.2	Option Summary.....	4
2.3	Configuration	11
2.4	Use of some signals	13
2.5	Examples	14
2.6	Agent's Assuan Protocol	14
2.6.1	Decrypting a session key	14
2.6.2	Signing a Hash	15
2.6.3	Generating a Key	16
2.6.4	Importing a Secret Key.....	17
2.6.5	Export a Secret Key	17
2.6.6	Importing a Root Certificate	17
2.6.7	Ask for a passphrase	18
2.6.8	Remove a cached passphrase.....	19
2.6.9	Set a passphrase for a keygrip	19
2.6.10	Ask for confirmation	19
2.6.11	Check whether a key is available.....	20
2.6.12	Register a smartcard	20
2.6.13	Change a Passphrase.....	20
2.6.14	Change the standard display	20
2.6.15	Get the Event Counters	20
2.6.16	Return information about the process	21
2.6.17	Set options for the session.....	21
3	Invoking DIRMNGR.....	23
3.1	Commands.....	23
3.2	Option Summary	24
3.3	Configuration	30
3.4	Use of signals	31
3.5	Examples	31
3.6	Dirmngr's Assuan Protocol.....	31
3.6.1	Return the certificate(s) found.....	31
3.6.2	Validate a certificate using a CRL or OCSP	32
3.6.3	Validate a certificate using a CRL	33
3.6.4	Validate a certificate using OCSP.....	33
3.6.5	Put a certificate into the internal cache.....	34
3.6.6	Validate a certificate for debugging	34

4	Invoking GPG	35
4.1	Commands	35
4.1.1	Commands not specific to the function	35
4.1.2	Commands to select the type of operation	35
4.1.3	How to manage your keys	42
4.2	Option Summary	50
4.2.1	How to change the configuration	50
4.2.2	Key related options	64
4.2.3	Input and Output	66
4.2.4	OpenPGP protocol specific options	71
4.2.5	Compliance options	73
4.2.6	Doing things one usually doesn't want to do	74
4.2.7	Deprecated options	84
4.3	Configuration files	85
4.4	Examples	87
4.5	Unattended Usage	90
4.5.1	Programmatic use of GnuPG	91
4.5.2	Ephemeral home directories	91
4.5.3	The quick key manipulation interface	91
4.5.4	Unattended key generation	91
5	Invoking GPGSM	97
5.1	Commands	97
5.1.1	Commands not specific to the function	97
5.1.2	Commands to select the type of operation	97
5.1.3	How to manage the certificates and keys	98
5.2	Option Summary	100
5.2.1	How to change the configuration	100
5.2.2	Certificate related options	101
5.2.3	Input and Output	103
5.2.4	How to change how the CMS is created	104
5.2.5	Doing things one usually do not want to do	104
5.3	Configuration files	106
5.4	Examples	108
5.5	Unattended Usage	108
5.5.1	Automated signature checking	108
5.5.2	CSR and certificate creation	109
5.6	The Protocol the Server Mode Uses	111
5.6.1	Encrypting a Message	111
5.6.2	Decrypting a message	112
5.6.3	Signing a Message	112
5.6.4	Verifying a Message	113
5.6.5	Generating a Key	113
5.6.6	List available keys	113
5.6.7	Export certificates	114
5.6.8	Import certificates	114
5.6.9	Delete certificates	115
5.6.10	Retrieve an audit log	115

5.6.11	Return information about the process	115
5.6.12	Session options.....	115
6	Invoking the SCDAEMON	119
6.1	Commands	119
6.2	Option Summary	119
6.3	Description of card applications	123
6.3.1	The OpenPGP card application “openpgp”	123
6.3.2	The Telesec NetKey card “nks”	123
6.3.3	The DINSIG card application “dinsig”	123
6.3.4	The PKCS#15 card application “p15”	123
6.3.5	The Geldkarte card application “geldkarte”	123
6.3.6	The SmartCard-HSM card application “sc-hsm”	123
6.3.7	The Undefined card application “undefined”	123
6.4	Configuration files	124
6.5	Examples	124
6.6	Scdaemon’s Assuan Protocol	124
6.6.1	Return the serial number	124
6.6.2	Read all useful information from the card.....	125
6.6.3	Return a certificate	125
6.6.4	Return a public key	125
6.6.5	Signing data with a Smartcard	125
6.6.6	Decrypting data with a Smartcard.....	125
6.6.7	Read an attribute’s value.....	126
6.6.8	Update an attribute’s value	126
6.6.9	Write a key to a card.....	126
6.6.10	Generate a new key on-card.....	126
6.6.11	Return random bytes generated on-card	126
6.6.12	Change PINs	126
6.6.13	Perform a VERIFY operation	126
6.6.14	Perform a RESTART operation	127
6.6.15	Send a verbatim APDU to the card	127
7	How to Specify a User Id.....	129
8	Trust Values	133

9	Helper Tools	135
9.1	Read logs from a socket	135
9.2	Verify OpenPGP signatures	136
9.2.1	Examples	137
9.2.2	Environment	137
9.2.3	FILES	138
9.3	Create .gnupg home directories	138
9.4	Modify .gnupg home directories	138
9.4.1	Invoking gpgconf	138
9.4.2	Format conventions	141
9.4.3	Listing components	143
9.4.4	Checking programs	143
9.4.5	Listing options	144
9.4.6	Changing options	147
9.4.7	Listing global options	148
9.4.8	Get and compare software versions	149
9.4.9	Files used by gpgconf	150
9.5	Run gpgconf for all users	150
9.6	Put a passphrase into the cache	150
9.6.1	List of all commands and options	150
9.7	Communicate with a running agent	151
9.7.1	List of all options	151
9.7.2	Control commands	152
9.8	The Dirmngr Client Tool	156
9.9	Parse a mail message into an annotated format	157
9.10	Call a simple symmetric encryption tool	157
9.10.1	List of all commands and options	158
9.11	Encrypt or sign files into an archive	159
10	Web Key Service	161
10.1	Send requests via WKS	161
10.2	Provide the Web Key Service	163
11	How to do certain things	167
11.1	Creating a TLS server certificate	167
12	Notes pertaining to certain OSes	173
12.1	Microsoft Windows Notes	173
13	How to solve problems	175
13.1	Debugging Tools	175
13.1.1	Scrutinizing a keybox file	175
13.2	Various hints on debugging	176
13.3	Commonly Seen Problems	176
13.4	How the whole thing works internally	178
13.4.1	How the components work together	178
13.4.2	Relationship between GnuPG 1.4 and 2.x	178

GNU General Public License	181
Preamble	181
TERMS AND CONDITIONS	182
How to Apply These Terms to Your New Programs	191
 Contributors to GnuPG	 193
 Glossary	 195
 Option Index	 197
 Environment Variable and File Index	 203
 Index	 205

1 A short installation guide

Unfortunately the installation guide has not been finished in time. Instead of delaying the release of GnuPG 2.0 even further, I decided to release without that guide. The chapter on `gpg-agent` and `gpgsm` do include brief information on how to set up the whole thing. Please watch the GnuPG website for updates of the documentation. In the meantime you may search the GnuPG mailing list archives or ask on the `gnupg-users` mailing list for advice on how to solve problems or how to get that whole thing up and running.

**** Building the software**

Building the software is described in the file `'INSTALL'`. Given that you are already reading this documentation we can only give some extra hints.

To comply with the rules on GNU systems you should have build time configured `gnupg` using:

```
./configure --sysconfdir=/etc --localstatedir=/var
```

This is to make sure that system wide configuration files are searched in the directory `'/etc'` and variable data below `'/var'`; the default would be to also install them below `'/usr/local'` where the binaries get installed. If you selected to use the `'--prefix=/'` you obviously don't need those option as they are the default then.

**** Notes on setting a root CA key to trusted**

X.509 is based on a hierarchical key infrastructure. At the root of the tree a trusted anchor (root certificate) is required. There are usually no other means of verifying whether this root certificate is trustworthy than looking it up in a list. GnuPG uses a file (`'trustlist.txt'`) to keep track of all root certificates it knows about. There are 3 ways to get certificates into this list:

- Use the list which comes with GnuPG. However this list only contains a few root certificates. Most installations will need more.
- Let `gpgsm` ask you whether you want to insert a new root certificate. This feature is enabled by default; you may disable it using the option `'no-allow-mark-trusted'` into `'gpg-agent.conf'`.
- Manually maintain the list of trusted root certificates. For a multi user installation this can be done once for all users on a machine. Specific changes on a per-user base are also possible.

2 Invoking GPG-AGENT

gpg-agent is a daemon to manage secret (private) keys independently from any protocol. It is used as a backend for **gpg** and **gpgsm** as well as for a couple of other utilities.

The agent is automatically started on demand by **gpg**, **gpgsm**, **gpgconf**, or **gpg-connect-agent**. Thus there is no reason to start it manually. In case you want to use the included Secure Shell Agent you may start the agent using:

```
gpg-connect-agent /bye
```

If you want to manually terminate the currently-running agent, you can safely do so with:

```
gpgconf --kill gpg-agent
```

You should always add the following lines to your **.bashrc** or whatever initialization file is used for all shell invocations:

```
GPG_TTY=$(tty)
export GPG_TTY
```

It is important that this environment variable always reflects the output of the **tty** command. For W32 systems this option is not required.

Please make sure that a proper pinentry program has been installed under the default filename (which is system dependent) or use the option '**pinentry-program**' to specify the full name of that program. It is often useful to install a symbolic link from the actual used pinentry (e.g. '**/usr/bin/pinentry-gtk**') to the expected one (e.g. '**/usr/bin/pinentry**'). See [\[Option Index\]](#), [page 197](#), for an index to GPG-AGENT's commands and options.

2.1 Commands

Commands are not distinguished from options except for the fact that only one command is allowed.

--version

Print the program version and licensing information. Note that you cannot abbreviate this command.

--help

-h Print a usage message summarizing the most useful command-line options. Note that you cannot abbreviate this command.

--dump-options

Print a list of all available options and commands. Note that you cannot abbreviate this command.

--server Run in server mode and wait for commands on the **stdin**. The default mode is to create a socket and listen for commands there.

--daemon [*command line*]

Start the **gpg-agent** as a daemon; that is, detach it from the console and run it in the background.

As an alternative you may create a new process as a child of **gpg-agent**: **gpg-agent --daemon /bin/sh**. This way you get a new shell with the environment setup properly; after you exit from this shell, **gpg-agent** terminates within a few seconds.

--supervised

Run in the foreground, sending logs by default to stderr, and listening on provided file descriptors, which must already be bound to listening sockets. This command is useful when running under systemd or other similar process supervision schemes. This option is not supported on Windows.

In `--supervised` mode, different file descriptors can be provided for use as different socket types (e.g. `ssh`, `extra`) as long as they are identified in the environment variable `LISTEN_FDNAMES` (see `sd_listen_fds(3)` on some Linux distributions for more information on this convention).

2.2 Option Summary

Options may either be used on the command line or, after stripping off the two leading dashes, in the configuration file.

--options *file*

Reads configuration from *file* instead of from the default per-user configuration file. The default configuration file is named `'gpg-agent.conf'` and expected in the `'gnupg'` directory directly below the home directory of the user. This option is ignored if used in an options file.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to `'~/.gnupg'`. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable `GNUPGHOME` or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named `'gpgconf.ct1'` in the same directory as the tool `'gpgconf.exe'`. The root of the installation is then that directory; or, if `'gpgconf.exe'` has been installed directly below a directory named `'bin'`, its parent directory. You also need to make sure that the following directories exist and are writable: `'ROOT/home'` for the GnuPG home and `'ROOT/var/cache/gnupg'` for internal cache files.

-v**--verbose**

Outputs additional information while running. You can increase the verbosity by giving several verbose commands to `gpg-agent`, such as `'-vv'`.

-q

--quiet Try to be as quiet as possible.

--batch Don't invoke a pinentry or do any other thing requiring human interaction.

--faked-system-time *epoch*

This option is only useful for testing; it sets the system time back or forth to *epoch* which is the number of seconds elapsed since the year 1970.

--debug-level *level*

Select the debug level for investigating problems. *level* may be a numeric value or a keyword:

none	No debugging at all. A value of less than 1 may be used instead of the keyword.
basic	Some basic debug messages. A value between 1 and 2 may be used instead of the keyword.
advanced	More verbose debug messages. A value between 3 and 5 may be used instead of the keyword.
expert	Even more detailed messages. A value between 6 and 8 may be used instead of the keyword.
guru	All of the debug messages you can get. A value greater than 8 may be used instead of the keyword. The creation of hash tracing files is only enabled if the keyword is used.

How these messages are mapped to the actual debugging flags is not specified and may change with newer releases of this program. They are however carefully selected to best aid in debugging.

--debug *flags*

This option is only useful for debugging and the behavior may change at any time without notice. FLAGS are bit encoded and may be given in usual C-Syntax. The currently defined bits are:

0 (1)	X.509 or OpenPGP protocol related data
1 (2)	values of big number integers
2 (4)	low level crypto operations
5 (32)	memory allocation
6 (64)	caching
7 (128)	show memory statistics
9 (512)	write hashed data to files named dbgmd-000*
10 (1024)	trace Assuan protocol
12 (4096)	bypass all certificate validation

--debug-all

Same as **--debug=0xffffffff**

--debug-wait *n*

When running in server mode, wait *n* seconds before entering the actual processing loop and print the pid. This gives time to attach a debugger.

--debug-quick-random

This option inhibits the use of the very secure random quality level (Libgcrypt's `GCRY_VERY_STRONG_RANDOM`) and degrades all request down to standard random quality. It is only used for testing and should not be used for any production quality keys. This option is only effective when given on the command line.

On GNU/Linux, another way to quickly generate insecure keys is to use `rngd` to fill the kernel's entropy pool with lower quality random data. `rngd` is typically provided by the `rng-tools` package. It can be run as follows: `'sudo rngd -f -r /dev/urandom'`.

--debug-pinentry

This option enables extra debug information pertaining to the Pinentry. As of now it is only useful when used along with `--debug 1024`.

--no-detach

Don't detach the process from the console. This is mainly useful for debugging.

-s**--sh****-c**

--csh Format the info output in daemon mode for use with the standard Bourne shell or the C-shell respectively. The default is to guess it based on the environment variable `SHELL` which is correct in almost all cases.

--grab**--no-grab**

Tell the pinentry to grab the keyboard and mouse. This option should be used on X-Servers to avoid X-sniffing attacks. Any use of the option `'--grab'` overrides an used option `'--no-grab'`. The default is `'--no-grab'`.

--log-file file

Append all logging output to *file*. This is very helpful in seeing what the agent actually does. Use `'socket://'` to log to socket. If neither a log file nor a log file descriptor has been set on a Windows platform, the Registry entry `HKCU\Software\GNU\GnuPG:DefaultLogFile`, if set, is used to specify the logging output.

--no-allow-mark-trusted

Do not allow clients to mark keys as trusted, i.e. put them into the `'trustlist.txt'` file. This makes it harder for users to inadvertently accept Root-CA keys.

--allow-preset-passphrase

This option allows the use of `gpg-preset-passphrase` to seed the internal cache of `gpg-agent` with passphrases.

--no-allow-loopback-pinentry**--allow-loopback-pinentry**

Disallow or allow clients to use the loopback pinentry features; see the option `'pinentry-mode'` for details. Allow is the default.

The `'--force'` option of the Assuan command `DELETE_KEY` is also controlled by this option: The option is ignored if a loopback pinentry is disallowed.

--no-allow-external-cache

Tell Pinentry not to enable features which use an external cache for passphrases.

Some desktop environments prefer to unlock all credentials with one master password and may have installed a Pinentry which employs an additional external cache to implement such a policy. By using this option the Pinentry is advised not to make use of such a cache and instead always ask the user for the requested passphrase.

--allow-emacs-pinentry

Tell Pinentry to allow features to divert the passphrase entry to a running Emacs instance. How this is exactly handled depends on the version of the used Pinentry.

--ignore-cache-for-signing

This option will let `gpg-agent` bypass the passphrase cache for all signing operation. Note that there is also a per-session option to control this behavior but this command line option takes precedence.

--default-cache-ttl *n*

Set the time a cache entry is valid to *n* seconds. The default is 600 seconds. Each time a cache entry is accessed, the entry's timer is reset. To set an entry's maximum lifetime, use `max-cache-ttl`. Note that a cached passphrase may not be evicted immediately from memory if no client requests a cache operation. This is due to an internal housekeeping function which is only run every few seconds.

--default-cache-ttl-ssh *n*

Set the time a cache entry used for SSH keys is valid to *n* seconds. The default is 1800 seconds. Each time a cache entry is accessed, the entry's timer is reset. To set an entry's maximum lifetime, use `max-cache-ttl-ssh`.

--max-cache-ttl *n*

Set the maximum time a cache entry is valid to *n* seconds. After this time a cache entry will be expired even if it has been accessed recently or has been set using `gpg-preset-passphrase`. The default is 2 hours (7200 seconds).

--max-cache-ttl-ssh *n*

Set the maximum time a cache entry used for SSH keys is valid to *n* seconds. After this time a cache entry will be expired even if it has been accessed recently or has been set using `gpg-preset-passphrase`. The default is 2 hours (7200 seconds).

--enforce-passphrase-constraints

Enforce the passphrase constraints by not allowing the user to bypass them using the "Take it anyway" button.

--min-passphrase-len *n*

Set the minimal length of a passphrase. When entering a new passphrase shorter than this value a warning will be displayed. Defaults to 8.

- min-passphrase-nonalpha *n***
 Set the minimal number of digits or special characters required in a passphrase. When entering a new passphrase with less than this number of digits or special characters a warning will be displayed. Defaults to 1.
- check-passphrase-pattern *file***
 Check the passphrase against the pattern given in *file*. When entering a new passphrase matching one of these pattern a warning will be displayed. *file* should be an absolute filename. The default is not to use any pattern file.
 Security note: It is known that checking a passphrase against a list of pattern or even against a complete dictionary is not very effective to enforce good passphrases. Users will soon figure up ways to bypass such a policy. A better policy is to educate users on good security behavior and optionally to run a passphrase cracker regularly on all users passphrases to catch the very simple ones.
- max-passphrase-days *n***
 Ask the user to change the passphrase if *n* days have passed since the last change. With ‘--enforce-passphrase-constraints’ set the user may not bypass this check.
- enable-passphrase-history**
 This option does nothing yet.
- pinentry-invisible-char *char***
 This option asks the Pinentry to use *char* for displaying hidden characters. *char* must be one character UTF-8 string. A Pinentry may or may not honor this request.
- pinentry-timeout *n***
 This option asks the Pinentry to timeout after *n* seconds with no user input. The default value of 0 does not ask the pinentry to timeout, however a Pinentry may use its own default timeout value in this case. A Pinentry may or may not honor this request.
- pinentry-program *filename***
 Use program *filename* as the PIN entry. The default is installation dependent. With the default configuration the name of the default pinentry is ‘pinentry’; if that file does not exist but a ‘pinentry-basic’ exist the latter is used.
 On a Windows platform the default is to use the first existing program from this list: ‘bin\pinentry.exe’, ‘..\Gpg4win\bin\pinentry.exe’, ‘..\Gpg4win\pinentry.exe’, ‘..\GNU\GnuPG\pinentry.exe’, ‘..\GNU\bin\pinentry.exe’, ‘bin\pinentry-basic.exe’ where the file names are relative to the GnuPG installation directory.
- pinentry-touch-file *filename***
 By default the filename of the socket gpg-agent is listening for requests is passed to Pinentry, so that it can touch that file before exiting (it does this only in curses mode). This option changes the file passed to Pinentry to *filename*. The special name /dev/null may be used to completely disable this feature. Note

that Pinentry will not create that file, it will only change the modification and access time.

--sddaemon-program *filename*

Use program *filename* as the Smartcard daemon. The default is installation dependent and can be shown with the **gpgconf** command.

--disable-sddaemon

Do not make use of the sddaemon tool. This option has the effect of disabling the ability to do smartcard operations. Note, that enabling this option at runtime does not kill an already forked sddaemon.

--disable-check-own-socket

gpg-agent employs a periodic self-test to detect a stolen socket. This usually means a second instance of **gpg-agent** has taken over the socket and **gpg-agent** will then terminate itself. This option may be used to disable this self-test for debugging purposes.

--use-standard-socket

--no-use-standard-socket

--use-standard-socket-p

Since GnuPG 2.1 the standard socket is always used. These options have no more effect. The command **gpg-agent --use-standard-socket-p** will thus always return success.

--display *string*

--ttyname *string*

--ttytype *string*

--lc-ctype *string*

--lc-messages *string*

--xauthority *string*

These options are used with the server mode to pass localization information.

--keep-tty

--keep-display

Ignore requests to change the current **tty** or X window system's **DISPLAY** variable respectively. This is useful to lock the pinentry to pop up at the **tty** or display you started the agent.

--listen-backlog *n*

Set the size of the queue for pending connections. The default is 64.

--extra-socket *name*

The extra socket is created by default, you may use this option to change the name of the socket. To disable the creation of the socket use "none" or "/dev/null" for *name*.

Also listen on native **gpg-agent** connections on the given socket. The intended use for this extra socket is to setup a Unix domain socket forwarding from a remote machine to this socket on the local machine. A **gpg** running on the remote machine may then connect to the local **gpg-agent** and use its private keys. This enables decrypting or signing data on a remote machine without exposing the private keys to the remote machine.

`--enable-extended-key-format`

`--disable-extended-key-format`

Since version 2.2.22 keys are created in the extended private key format by default. Changing the passphrase of a key will also convert the key to that new format. This key format is supported since GnuPG version 2.1.12 and thus there should be no need to disable it. Anyway, the disable option still allows to revert to the old behavior for new keys; be aware that keys are never migrated back to the old format. If the enable option has been used the disable option won't have an effect. The advantage of the extended private key format is that it is text based and can carry additional meta data. In extended key format the OCB mode is used for key protection.

`--enable-ssh-support`

`--enable-putty-support`

The OpenSSH Agent protocol is always enabled, but `gpg-agent` will only set the `SSH_AUTH_SOCK` variable if this flag is given.

In this mode of operation, the agent does not only implement the `gpg-agent` protocol, but also the agent protocol used by OpenSSH (through a separate socket). Consequently, it should be possible to use the `gpg-agent` as a drop-in replacement for the well known `ssh-agent`.

SSH Keys, which are to be used through the agent, need to be added to the `gpg-agent` initially through the `ssh-add` utility. When a key is added, `ssh-add` will ask for the password of the provided key file and send the unprotected key material to the agent; this causes the `gpg-agent` to ask for a passphrase, which is to be used for encrypting the newly received key and storing it in a `gpg-agent` specific directory.

Once a key has been added to the `gpg-agent` this way, the `gpg-agent` will be ready to use the key.

Note: in case the `gpg-agent` receives a signature request, the user might need to be prompted for a passphrase, which is necessary for decrypting the stored key. Since the `ssh-agent` protocol does not contain a mechanism for telling the agent on which display/terminal it is running, `gpg-agent`'s `ssh-support` will use the TTY or X display where `gpg-agent` has been started. To switch this display to the current one, the following command may be used:

```
gpg-connect-agent updatestartuptty /bye
```

Although all GnuPG components try to start the `gpg-agent` as needed, this is not possible for the `ssh` support because `ssh` does not know about it. Thus if no GnuPG tool which accesses the agent has been run, there is no guarantee that `ssh` is able to use `gpg-agent` for authentication. To fix this you may start `gpg-agent` if needed using this simple command:

```
gpg-connect-agent /bye
```

Adding the '`--verbose`' shows the progress of starting the agent.

The '`--enable-putty-support`' is only available under Windows and allows the use of `gpg-agent` with the `ssh` implementation `putty`. This is similar to the regular `ssh-agent` support but makes use of Windows message queue as required by `putty`.

--ssh-fingerprint-digest

Select the digest algorithm used to compute ssh fingerprints that are communicated to the user, e.g. in pinentry dialogs. OpenSSH has transitioned from using MD5 to the more secure SHA256.

--auto-expand-secmem *n*

Allow Libgcrypt to expand its secure memory area as required. The optional value *n* is a non-negative integer with a suggested size in bytes of each additionally allocated secure memory area. The value is rounded up to the next 32 KiB; usual C style prefixes are allowed. For an heavily loaded gpg-agent with many concurrent connection this option avoids sign or decrypt errors due to out of secure memory error returns.

--s2k-calibration *milliseconds*

Change the default calibration time to *milliseconds*. The given value is capped at 60 seconds; a value of 0 resets to the compiled-in default. This option is re-read on a SIGHUP (or `gpgconf --reload gpg-agent`) and the S2K count is then re-calibrated.

--s2k-count *n*

Specify the iteration count used to protect the passphrase. This option can be used to override the auto-calibration done by default. The auto-calibration computes a count which requires by default 100ms to mangle a given passphrase. See also ‘`--s2k-calibration`’.

To view the actually used iteration count and the milliseconds required for an S2K operation use:

```
gpg-connect-agent 'GETINFO s2k_count' /bye
gpg-connect-agent 'GETINFO s2k_time' /bye
```

To view the auto-calibrated count use:

```
gpg-connect-agent 'GETINFO s2k_count_cal' /bye
```

2.3 Configuration

There are a few configuration files needed for the operation of the agent. By default they may all be found in the current home directory (see [option `--homedir`], page 4).

‘gpg-agent.conf’

This is the standard configuration file read by `gpg-agent` on startup. It may contain any valid long option; the leading two dashes may not be entered and the option may not be abbreviated. This file is also read after a SIGHUP however only a few options will actually have an effect. This default name may be changed on the command line (see [option `--options`], page 4). You should backup this file.

‘trustlist.txt’

This is the list of trusted keys. You should backup this file.

Comment lines, indicated by a leading hash mark, as well as empty lines are ignored. To mark a key as trusted you need to enter its fingerprint followed by a space and a capital letter S. Colons may optionally be used to separate the

bytes of a fingerprint; this enables cutting and pasting the fingerprint from a key listing output. If the line is prefixed with a `!` the key is explicitly marked as not trusted.

Here is an example where two keys are marked as ultimately trusted and one as not trusted:

```
# CN=Wurzel ZS 3,O=Intevation GmbH,C=DE
A6935DD34EF3087973C706FC311AA2CCF733765B S

# CN=PCA-1-Verwaltung-02/O=PKI-1-Verwaltung/C=DE
DC:BD:69:25:48:BD:BB:7E:31:6E:BB:80:D3:00:80:35:D4:F8:A6:CD S

# CN=Root-CA/O=Schlapphuete/L=Pullach/C=DE
!14:56:98:D3:FE:9C:CA:5A:31:6E:BC:81:D3:11:4E:00:90:A3:44:C2 S
```

Before entering a key into this file, you need to ensure its authenticity. How to do this depends on your organisation; your administrator might have already entered those keys which are deemed trustworthy enough into this file. Places where to look for the fingerprint of a root certificate are letters received from the CA or the website of the CA (after making 100% sure that this is indeed the website of that CA). You may want to consider disallowing interactive updates of this file by using the [\[option `--no-allow-mark-trusted`\]](#), [page 6](#). It might even be advisable to change the permissions to read-only so that this file can't be changed inadvertently.

As a special feature a line `include-default` will include a global list of trusted certificates (e.g. `/etc/gnupg/trustlist.txt`). This global list is also used if the local list is not available.

It is possible to add further flags after the `S` for use by the caller:

<code>relax</code>	Relax checking of some root certificate requirements. As of now this flag allows the use of root certificates with a missing basic-Constraints attribute (despite that it is a MUST for CA certificates) and disables CRL checking for the root certificate.
<code>cm</code>	If validation of a certificate finally issued by a CA with this flag set fails, try again using the chain validation model.

`'sshcontrol'`

This file is used when support for the secure shell agent protocol has been enabled (see [\[option `--enable-ssh-support`\]](#), [page 10](#)). Only keys present in this file are used in the SSH protocol. You should backup this file.

The `ssh-add` tool may be used to add new entries to this file; you may also add them manually. Comment lines, indicated by a leading hash mark, as well as empty lines are ignored. An entry starts with optional whitespace, followed by the keygrip of the key given as 40 hex digits, optionally followed by the caching TTL in seconds and another optional field for arbitrary flags. A non-zero TTL overrides the global default as set by `'--default-cache-ttl-ssh'`.

The only flag support is `confirm`. If this flag is found for a key, each use of the key will pop up a pinentry to confirm the use of that key. The flag is

automatically set if a new key was loaded into `gpg-agent` using the option `‘-c’` of the `ssh-add` command.

The keygrip may be prefixed with a `!` to disable an entry.

The following example lists exactly one key. Note that keys available through a OpenPGP smartcard in the active smartcard reader are implicitly added to this list; i.e. there is no need to list them.

```
# Key added on: 2011-07-20 20:38:46
# Fingerprint: 5e:8d:c4:ad:e7:af:6e:27:8a:d6:13:e4:79:ad:0b:81
34B62F25E277CF13D3C6BCEBFD3F85D08F0A864B 0 confirm
```

`‘private-keys-v1.d/’`

This is the directory where `gpg-agent` stores the private keys. Each key is stored in a file with the name made up of the keygrip and the suffix `‘key’`. You should backup all files in this directory and take great care to keep this backup closed away.

Note that on larger installations, it is useful to put predefined files into the directory `‘/etc/skel/.gnupg’` so that newly created users start up with a working configuration. For existing users the a small helper script is provided to create these files (see [Section 9.3 \[addgnupghome\]](#), page 138).

2.4 Use of some signals

A running `gpg-agent` may be controlled by signals, i.e. using the `kill` command to send a signal to the process.

Here is a list of supported signals:

- | | |
|---------|--|
| SIGHUP | This signal flushes all cached passphrases and if the program has been started with a configuration file, the configuration file is read again. Only certain options are honored: <code>quiet</code> , <code>verbose</code> , <code>debug</code> , <code>debug-all</code> , <code>debug-level</code> , <code>debug-pinentry</code> , <code>no-grab</code> , <code>pinentry-program</code> , <code>pinentry-invisible-char</code> , <code>default-cache-ttl</code> , <code>max-cache-ttl</code> , <code>ignore-cache-for-signing</code> , <code>s2k-count</code> , <code>no-allow-external-cache</code> , <code>allow-emacs-pinentry</code> , <code>no-allow-mark-trusted</code> , <code>disable-scd daemon</code> , and <code>disable-check-own-socket</code> . <code>scdaemon-program</code> is also supported but due to the current implementation, which calls the <code>scdaemon</code> only once, it is not of much use unless you manually kill the <code>scdaemon</code> . |
| SIGTERM | Shuts down the process but waits until all current requests are fulfilled. If the process has received 3 of these signals and requests are still pending, a shutdown is forced. |
| SIGINT | Shuts down the process immediately. |
| SIGUSR1 | Dump internal information to the log file. |
| SIGUSR2 | This signal is used for internal purposes. |

2.5 Examples

It is important to set the environment variable `GPG_TTY` in your login shell, for example in the `~/ .bashrc` init script:

```
export GPG_TTY=$(tty)
```

If you enabled the Ssh Agent Support, you also need to tell ssh about it by adding this to your init script:

```
unset SSH_AGENT_PID
if [ "${gnupg_SSH_AUTH_SOCK_by:-0}" -ne $$ ]; then
    export SSH_AUTH_SOCK="$(gpgconf --list-dirs agent-ssh-socket)"
fi
```

2.6 Agent's Assuan Protocol

Note: this section does only document the protocol, which is used by GnuPG components; it does not deal with the ssh-agent protocol. To see the full specification of each command, use

```
gpg-connect-agent 'help COMMAND' /bye
```

or just 'help' to list all available commands.

The `gpg-agent` daemon is started on demand by the GnuPG components.

To identify a key we use a thing called keygrip which is the SHA-1 hash of an canonical encoded S-Expression of the public key as used in Libgcrypt. For the purpose of this interface the keygrip is given as a hex string. The advantage of using this and not the hash of a certificate is that it will be possible to use the same keypair for different protocols, thereby saving space on the token used to keep the secret keys.

The `gpg-agent` may send status messages during a command or when returning from a command to inform a client about the progress or result of an operation. For example, the `INQUIRE_MAXLEN` status message may be sent during a server inquire to inform the client of the maximum usable length of the inquired data (which should not be exceeded).

2.6.1 Decrypting a session key

The client asks the server to decrypt a session key. The encrypted session key should have all information needed to select the appropriate secret key or to delegate it to a smartcard.

```
SETKEY <keyGrip>
```

Tell the server about the key to be used for decryption. If this is not used, `gpg-agent` may try to figure out the key by trying to decrypt the message with each key available.

```
PKDECRYPT
```

The agent checks whether this command is allowed and then does an `INQUIRE` to get the ciphertext the client should then send the cipher text.

```
S: INQUIRE CIPHERTEXT
C: D (xxxxxx)
```



```
C: D xxxx)
C: END
```

Please note that the server may send status info lines while reading the data lines from the client. The data send is a SPKI like S-Exp with this structure:

```
(enc-val
  (<algo>
    (<param_name1> <mpi>)
    ...
    (<param_namen> <mpi>)))
```

Where algo is a string with the name of the algorithm; see the libgcrypt documentation for a list of valid algorithms. The number and names of the parameters depend on the algorithm. The agent does return an error if there is an inconsistency.

If the decryption was successful the decrypted data is returned by means of "D" lines.

Here is an example session:

```
C: PKDECRYPT
S: INQUIRE CIPHERTEXT
C: D (enc-val elg (a 349324324)
C: D (b 3F444677CA)))
C: END
S: # session key follows
S: S PADDING 0
S: D (value 1234567890ABCDEF0)
S: OK decryption successful
```

The PADDING status line is only send if gpg-agent can tell what kind of padding is used. As of now only the value 0 is used to indicate that the padding has been removed.

2.6.2 Signing a Hash

The client asks the agent to sign a given hash value. A default key will be chosen if no key has been set. To set a key a client first uses:

```
SIGKEY <keyGrip>
```

This can be used multiple times to create multiple signature, the list of keys is reset with the next PKSIGN command or a RESET. The server tests whether the key is a valid key to sign something and responds with okay.

```
SETHASH --hash=<name>|<algo> <hexstring>
```

The client can use this command to tell the server about the data <hexstring> (which usually is a hash) to be signed. <algo> is the decimal encoded hash algorithm number as used by Libgcrypt. Either <algo> or --hash=<name> must be given. Valid names for <name> are:

sha1	The SHA-1 hash algorithm
sha256	The SHA-256 hash algorithm
rm160	The RIPE-MD160 hash algorithm
md5	The old and broken MD5 hash algorithm

tls-md5sha1

A combined hash algorithm as used by the TLS protocol.

The actual signing is done using

PKSIGN <options>

Options are not yet defined, but may later be used to choose among different algorithms. The agent does then some checks, asks for the passphrase and as a result the server returns the signature as an SPKI like S-expression in "D" lines:

```
(sig-val
  (<algo>
    (<param_name1> <mpi>))
  ...
  (<param_namen> <mpi>)))
```

The operation is affected by the option

OPTION use-cache-for-signing=0|1

The default of 1 uses the cache. Setting this option to 0 will lead **gpg-agent** to ignore the passphrase cache. Note, that there is also a global command line option for **gpg-agent** to globally disable the caching.

Here is an example session:

```
C: SIGKEY <keyGrip>
S: OK key available
C: SIGKEY <keyGrip>
S: OK key available
C: PKSIGN
S: # I did ask the user whether he really wants to sign
S: # I did ask the user for the passphrase
S: INQUIRE HASHVAL
C: D ABCDEF012345678901234
C: END
S: # signature follows
S: D (sig-val rsa (s 45435453654612121212))
S: OK
```

2.6.3 Generating a Key

This is used to create a new keypair and store the secret key inside the active PSE — which is in most cases a Soft-PSE. A not-yet-defined option allows choosing the storage location. To get the secret key out of the PSE, a special export tool has to be used.

GENKEY [--no-protection] [--preset] [<cache_nonce>]

Invokes the key generation process and the server will then inquire on the generation parameters, like:

```
S: INQUIRE KEYPARM
C: D (genkey (rsa (nbits 1024)))
C: END
```

The format of the key parameters which depends on the algorithm is of the form:

```
(genkey
  (algo
    (parameter_name_1 ....)
    ....
    (parameter_name_n ....)))
```

If everything succeeds, the server returns the *public key* in a SPKI like S-Expression like this:

```
(public-key
  (rsa
    (n <mpi>)
    (e <mpi>)))
```

Here is an example session:

```
C: GENKEY
S: INQUIRE KEYPARM
C: D (genkey (rsa (nbits 1024)))
C: END
S: D (public-key
S: D   (rsa (n 326487324683264) (e 10001)))
S  OK key created
```

The ‘`--no-protection`’ option may be used to prevent prompting for a passphrase to protect the secret key while leaving the secret key unprotected. The ‘`--preset`’ option may be used to add the passphrase to the cache using the default cache parameters.

The ‘`--inq-passwd`’ option may be used to create the key with a supplied passphrase. When used the agent does an inquiry with the keyword `NEWPASSWD` to retrieve that passphrase. This option takes precedence over ‘`--no-protection`’; however if the client sends a empty (zero-length) passphrase, this is identical to ‘`--no-protection`’.

2.6.4 Importing a Secret Key

This operation is not yet supported by GpgAgent. Specialized tools are to be used for this.

There is no actual need because we can expect that secret keys created by a 3rd party are stored on a smartcard. If we have generated the key ourselves, we do not need to import it.

2.6.5 Export a Secret Key

Not implemented.

Should be done by an extra tool.

2.6.6 Importing a Root Certificate

Actually we do not import a Root Cert but provide a way to validate any piece of data by storing its Hash along with a description and an identifier in the PSE. Here is the interface description:

```
ISTRUSTED <fingerprint>
```

Check whether the OpenPGP primary key or the X.509 certificate with the given fingerprint is an ultimately trusted key or a trusted Root CA certificate. The fingerprint should

be given as a hexstring (without any blanks or colons or whatever in between) and may be left padded with 00 in case of an MD5 fingerprint. GPGAgent will answer with:

OK

The key is in the table of trusted keys.

ERR 304 (Not Trusted)

The key is not in this table.

Gpg needs the entire list of trusted keys to maintain the web of trust; the following command is therefore quite helpful:

LISTTRUSTED

GpgAgent returns a list of trusted keys line by line:

```
S: D 000000001234454556565656677878AF2F1ECCFF P
S: D 340387563485634856435645634856438576457A P
S: D FEDC6532453745367FD83474357495743757435D S
S: OK
```

The first item on a line is the hexified fingerprint where MD5 fingerprints are 00 padded to the left and the second item is a flag to indicate the type of key (so that gpg is able to only take care of PGP keys). P = OpenPGP, S = S/MIME. A client should ignore the rest of the line, so that we can extend the format in the future.

Finally a client should be able to mark a key as trusted:

MARKTRUSTED *fingerprint* "P"|"S"

The server will then pop up a window to ask the user whether she really trusts this key. For this it will probably ask for a text to be displayed like this:

```
S: INQUIRE TRUSTDESC
C: D Do you trust the key with the fingerprint @FPR@
C: D bla fasel blurb.
C: END
S: OK
```

Known sequences with the pattern @foo@ are replaced according to this table:

@FPR16@	Format the fingerprint according to gpg rules for a v3 keys.
@FPR20@	Format the fingerprint according to gpg rules for a v4 keys.
@FPR@	Choose an appropriate format to format the fingerprint.
@@	Replaced by a single @.

2.6.7 Ask for a passphrase

This function is usually used to ask for a passphrase to be used for symmetric encryption, but may also be used by programs which need special handling of passphrases. This command uses a syntax which helps clients to use the agent with minimum effort.

```
GET_PASSPHRASE [--data] [--check] [--no-ask] [--repeat[=N]] \
                [--qualitybar] cache_id \
                [error_message prompt description]
```

cache_id is expected to be a string used to identify a cached passphrase. Use a X to bypass the cache. With no other arguments the agent returns a cached passphrase or an

error. By convention either the hexified fingerprint of the key shall be used for *cache_id* or an arbitrary string prefixed with the name of the calling application and a colon: Like `gpg:somestring`.

error_message is either a single `X` for no error message or a string to be shown as an error message like (e.g. "invalid passphrase"). Blanks must be percent escaped or replaced by `+`.

prompt is either a single `X` for a default prompt or the text to be shown as the prompt. Blanks must be percent escaped or replaced by `+`.

description is a text shown above the entry field. Blanks must be percent escaped or replaced by `+`.

The agent either returns with an error or with a `OK` followed by the hex encoded passphrase. Note that the length of the strings is implicitly limited by the maximum length of a command. If the option `--data` is used, the passphrase is not returned on the `OK` line but by regular data lines; this is the preferred method.

If the option `--check` is used, the standard passphrase constraints checks are applied. A check is not done if the passphrase has been found in the cache.

If the option `--no-ask` is used and the passphrase is not in the cache the user will not be asked to enter a passphrase but the error code `GPG_ERR_NO_DATA` is returned.

If the option `--qualitybar` is used and a minimum passphrase length has been configured, a visual indication of the entered passphrase quality is shown.

`CLEAR_PASSPHRASE` *cache_id*

may be used to invalidate the cache entry for a passphrase. The function returns with `OK` even when there is no cached passphrase.

2.6.8 Remove a cached passphrase

Use this command to remove a cached passphrase.

`CLEAR_PASSPHRASE` `[--mode=normal]` *<cache_id>*

The `--mode=normal` option can be used to clear a *cache_id* that was set by `gpg-agent`.

2.6.9 Set a passphrase for a keygrip

This command adds a passphrase to the cache for the specified *keygrip*.

`PRESET_PASSPHRASE` `[--inquire]` *<string_or_keygrip>* *<timeout>* [*<hexstring>*]

The passphrase is a hexadecimal string when specified. When not specified, the passphrase will be retrieved from the `pinentry` module unless the `--inquire` option was specified in which case the passphrase will be retrieved from the client.

The *timeout* parameter keeps the passphrase cached for the specified number of seconds. A value of `-1` means infinite while `0` means the default (currently only a timeout of `-1` is allowed, which means to never expire it).

2.6.10 Ask for confirmation

This command may be used to ask for a simple confirmation by presenting a text and 2 buttons: `Okay` and `Cancel`.

GET_CONFIRMATION *description*

description is displayed along with a Okay and Cancel button. Blanks must be percent escaped or replaced by +. A X may be used to display confirmation dialog with a default text.

The agent either returns with an error or with a OK. Note, that the length of *description* is implicitly limited by the maximum length of a command.

2.6.11 Check whether a key is available

This can be used to see whether a secret key is available. It does not return any information on whether the key is somehow protected.

HAVEKEY *keygrips*

The agent answers either with OK or No_Secret_Key (208). The caller may want to check for other error codes as well. More than one keygrip may be given. In this case the command returns success if at least one of the keygrips corresponds to an available secret key.

2.6.12 Register a smartcard**LEARN [--send]**

This command is used to register a smartcard. With the ‘--send’ option given the certificates are sent back.

2.6.13 Change a Passphrase**PASSWD [--cache-nonce=<c>] [--passwd-nonce=<s>] [--preset] *keygrip***

This command is used to interactively change the passphrase of the key identified by the hex string *keygrip*. The ‘--preset’ option may be used to add the new passphrase to the cache using the default cache parameters.

2.6.14 Change the standard display**UPDATESTARTUPTY**

Set the startup TTY and X-DISPLAY variables to the values of this session. This command is useful to direct future pinentry invocations to another screen. It is only required because there is no way in the ssh-agent protocol to convey this information.

2.6.15 Get the Event Counters**GETEVENTCOUNTER**

This function return one status line with the current values of the event counters. The event counters are useful to avoid polling by delaying a poll until something has changed. The values are decimal numbers in the range 0 to UINT_MAX and wrapping around to 0. The actual values should not be relied upon; they shall only be used to detect a change.

The currently defined counters are:

ANY	Incremented with any change of any of the other counters.
KEY	Incremented for added or removed private keys.
CARD	Incremented for changes of the card readers stati.

2.6.16 Return information about the process

This is a multipurpose function to return a variety of information.

`GETINFO what`

The value of *what* specifies the kind of information returned:

version Return the version of the program.

pid Return the process id of the process.

socket_name
 Return the name of the socket used to connect the agent.

ssh_socket_name
 Return the name of the socket used for SSH connections. If SSH support has not been enabled the error `GPG_ERR_NO_DATA` will be returned.

2.6.17 Set options for the session

Here is a list of session options which are not yet described with other commands. The general syntax for an Assuan option is:

`OPTION key=value`

Supported *keys* are:

agent-awareness
 This may be used to tell gpg-agent of which gpg-agent version the client is aware of. gpg-agent uses this information to enable features which might break older clients.

putenv Change the session's environment to be used for the Pinentry. Valid values are:

name Delete envvar *name*

name= Set envvar *name* to the empty string

name=value Set envvar *name* to the string *value*.

use-cache-for-signing
 See Assuan command `PKSIGN`.

allow-pinentry-notify
 This does not need any value. It is used to enable the `PINENTRY_LAUNCHED` inquiry.

pinentry-mode
 This option is used to change the operation mode of the pinentry. The following values are defined:

ask This is the default mode which pops up a pinentry as needed.

cancel Instead of popping up a pinentry, return the error code `GPG_ERR_CANCELED`.

error Instead of popping up a pinentry, return the error code `GPG_ERR_NO_PIN_ENTRY`.

loopback Use a loopback pinentry. This fakes a pinentry by using inquiries back to the caller to ask for a passphrase. This option may only be set if the agent has been configured for that. To disable this feature use `[option -no-allow-loopback-pinentry]`, page 6.

cache-ttl-opt-preset

This option sets the cache TTL for new entries created by GENKEY and PASSWD commands when using the ‘`--preset`’ option. It is not used a default value is used.

s2k-count

Instead of using the standard S2K count (which is computed on the fly), the given S2K count is used for new keys or when changing the passphrase of a key. Values below 65536 are considered to be 0. This option is valid for the entire session or until reset to 0. This option is useful if the key is later used on boxes which are either much slower or faster than the actual box.

pretend-request-origin

This option switches the connection into a restricted mode which handles all further commands in the same way as they would be handled when originating from the extra or browser socket. Note that this option is not available in the restricted mode. Valid values for this option are:

none

local This is a NOP and leaves the connection in the standard way.

remote Pretend to come from a remote origin in the same way as connections from the ‘`--extra-socket`’.

browser Pretend to come from a local web browser in the same way as connections from the ‘`--browser-socket`’.

3 Invoking DIRMNGR

Since version 2.1 of GnuPG, `dirmngr` takes care of accessing the OpenPGP keyserver. As with previous versions it is also used as a server for managing and downloading certificate revocation lists (CRLs) for X.509 certificates, downloading X.509 certificates, and providing access to OCSP providers. `Dirmngr` is invoked internally by `gpg`, `gpgsm`, or via the `gpg-connect-agent` tool.

See [\[Option Index\]](#), page 197, for an index to DIRMNGR's commands and options.

3.1 Commands

Commands are not distinguished from options except for the fact that only one command is allowed.

- `--version`
Print the program version and licensing information. Note that you cannot abbreviate this command.
- `--help, -h`
Print a usage message summarizing the most useful command-line options. Note that you cannot abbreviate this command.
- `--dump-options`
Print a list of all available options and commands. Note that you cannot abbreviate this command.
- `--server` Run in server mode and wait for commands on the `stdin`. The default mode is to create a socket and listen for commands there. This is only used for testing.
- `--daemon` Run in background daemon mode and listen for commands on a socket. This is the way `dirmngr` is started on demand by the other GnuPG components. To force starting `dirmngr` it is in general best to use `gpgconf --launch dirmngr`.
- `--supervised`
Run in the foreground, sending logs to `stderr`, and listening on file descriptor 3, which must already be bound to a listening socket. This is useful when running under `systemd` or other similar process supervision schemes. This option is not supported on Windows.
- `--list-crls`
List the contents of the CRL cache on `stdout`. This is probably only useful for debugging purposes.
- `--load-crl file`
This command requires a filename as additional argument, and it will make `Dirmngr` try to import the CRL in *file* into its cache. Note, that this is only possible if `Dirmngr` is able to retrieve the CA's certificate directly by its own means. In general it is better to use `gpgsm`'s `--call-dirmngr loadcrl filename` command so that `gpgsm` can help `dirmngr`.
- `--fetch-crl url`
This command requires an URL as additional argument, and it will make `dirmngr` try to retrieve and import the CRL from that *url* into its cache. This is

mainly useful for debugging purposes. The `dirmngr-client` provides the same feature for a running `dirmngr`.

--shutdown

This command shuts down an running instance of `Dirmngr`. This command has currently no effect.

--flush

This command removes all CRLs from `Dirmngr`'s cache. Client requests will thus trigger reading of fresh CRLs.

3.2 Option Summary

Note that all long options with the exception of '`--options`' and '`--homedir`' may also be given in the configuration file after stripping off the two leading dashes.

--options *file*

Reads configuration from *file* instead of from the default per-user configuration file. The default configuration file is named '`dirmngr.conf`' and expected in the home directory.

--homedir *dir*

Set the name of the home directory to *dir*. This option is only effective when used on the command line. The default is the directory named '`.gnupg`' directly below the home directory of the user unless the environment variable `GNUPGHOME` has been set in which case its value will be used. Many kinds of data are stored within this directory.

-v

--verbose

Outputs additional information while running. You can increase the verbosity by giving several verbose commands to `DIRMNGR`, such as '`-vv`'.

--log-file *file*

Append all logging output to *file*. This is very helpful in seeing what the agent actually does. Use '`socket://`' to log to socket.

--debug-level *level*

Select the debug level for investigating problems. *level* may be a numeric value or by a keyword:

none	No debugging at all. A value of less than 1 may be used instead of the keyword.
basic	Some basic debug messages. A value between 1 and 2 may be used instead of the keyword.
advanced	More verbose debug messages. A value between 3 and 5 may be used instead of the keyword.
expert	Even more detailed messages. A value between 6 and 8 may be used instead of the keyword.
guru	All of the debug messages you can get. A value greater than 8 may be used instead of the keyword. The creation of hash tracing files is only enabled if the keyword is used.

How these messages are mapped to the actual debugging flags is not specified and may change with newer releases of this program. They are however carefully selected to best aid in debugging.

--debug *flags*

Set debugging flags. This option is only useful for debugging and its behavior may change with a new release. All flags are or-ed and may be given in C syntax (e.g. 0x0042) or as a comma separated list of flag names. To get a list of all supported flags the single word "help" can be used.

--debug-all

Same as **--debug=0xffffffff**

--tls-debug *level*

Enable debugging of the TLS layer at *level*. The details of the debug level depend on the used TLS library and are not set in stone.

--debug-wait *n*

When running in server mode, wait *n* seconds before entering the actual processing loop and print the pid. This gives time to attach a debugger.

--disable-check-own-socket

On some platforms **dirmngr** is able to detect the removal of its socket file and shutdown itself. This option disable this self-test for debugging purposes.

-s

--sh

-c

--csh Format the info output in daemon mode for use with the standard Bourne shell respective the C-shell. The default is to guess it based on the environment variable **SHELL** which is in almost all cases sufficient.

--force Enabling this option forces loading of expired CRLs; this is only useful for debugging.

--use-tor

--no-use-tor

The option '**--use-tor**' switches **Dirmngr** and thus **GnuPG** into "Tor mode" to route all network access via Tor (an anonymity network). Certain other features are disabled in this mode. The effect of '**--use-tor**' cannot be overridden by any other command or even by reloading **dirmngr**. The use of '**--no-use-tor**' disables the use of Tor. The default is to use Tor if it is available on startup or after reloading **dirmngr**.

--standard-resolver

This option forces the use of the system's standard DNS resolver code. This is mainly used for debugging. Note that on Windows a standard resolver is not used and all DNS access will return the error "Not Implemented" if this option is used. Using this together with enabled Tor mode returns the error "Not Enabled".

--recursive-resolver

When possible use a recursive resolver instead of a stub resolver.

--resolver-timeout *n*

Set the timeout for the DNS resolver to *N* seconds. The default are 30 seconds.

--connect-timeout *n***--connect-quick-timeout *n***

Set the timeout for HTTP and generic TCP connection attempts to *N* seconds. The value set with the quick variant is used when the `--quick` option has been given to certain Assuan commands. The quick value is capped at the value of the regular connect timeout. The default values are 15 and 2 seconds. Note that the timeout values are for each connection attempt; the connection code will attempt to connect all addresses listed for a server.

--listen-backlog *n*

Set the size of the queue for pending connections. The default is 64.

--allow-version-check

Allow Dirmngr to connect to <https://versions.gnupg.org> to get the list of current software versions. If this option is enabled the list is retrieved in case the local copy does not exist or is older than 5 to 7 days. See the option `'--query-swdb'` of the command `gpgconf` for more details. Note, that regardless of this option a version check can always be triggered using this command:

```
gpg-connect-agent --dirmngr 'loadswdb --force' /bye
```

--keyserver *name*

Use *name* as your keyserver. This is the server that `gpg` communicates with to receive keys, send keys, and search for keys. The format of the *name* is a URI: `'scheme:[//]keyservername[:port]'`. The scheme is the type of keyserver: `"hkp"` for the HTTP (or compatible) keystores, `"ldap"` for the LDAP keystores, or `"mailto"` for the Graff email keyserver. Note that your particular installation of GnuPG may have other keyserver types available as well. Keyserver schemes are case-insensitive. After the keyserver name, optional keyserver configuration options may be provided. These are the same as the `'--keyserver-options'` of `gpg`, but apply only to this particular keyserver.

Most keystores synchronize with each other, so there is generally no need to send keys to more than one server. The keyserver `hkp://keys.gnupg.net` uses round robin DNS to give a different keyserver each time you use it.

If exactly two keystores are configured and only one is a Tor hidden service (`.onion`), Dirmngr selects the keyserver to use depending on whether Tor is locally running or not. The check for a running Tor is done for each new connection.

If no keyserver is explicitly configured, dirmngr will use the built-in default of `hkps://hkps.pool.sks-keyservers.net`.

Windows users with a keyserver running on their Active Directory should use `ldap:///` for *name* to access this directory.

For accessing anonymous LDAP keystores *name* is in general just a `ldap://ldap.example.com`. A BaseDN parameter should never be specified. If authentication is required the value of *name* is for example:

```
keyserver ldaps://ldap.example.com/????bindname=uid=USERNAME%2C%2Cdc=com,password=PASSWORD
```

Put this all on one line without any spaces and keep the '%2C' as given. Replace USERNAME, PASSWORD, and the 'dc' parts according to the instructions received from the LDAP administrator. Note that only simple authentication (i.e. cleartext passwords) is supported and thus using ldaps is strongly suggested.

--nameserver *ipaddr*

In “Tor mode” Dirmngr uses a public resolver via Tor to resolve DNS names. If the default public resolver, which is 8.8.8.8, shall not be used a different one can be given using this option. Note that a numerical IP address must be given (IPv6 or IPv4) and that no error checking is done for *ipaddr*.

--disable-ipv4

--disable-ipv6

Disable the use of all IPv4 or IPv6 addresses.

--disable-ldap

Entirely disables the use of LDAP.

--disable-http

Entirely disables the use of HTTP.

--ignore-http-dp

When looking for the location of a CRL, the to be tested certificate usually contains so called *CRL Distribution Point* (DP) entries which are URLs describing the way to access the CRL. The first found DP entry is used. With this option all entries using the HTTP scheme are ignored when looking for a suitable DP.

--ignore-ldap-dp

This is similar to ‘--ignore-http-dp’ but ignores entries using the LDAP scheme. Both options may be combined resulting in ignoring DPs entirely.

--ignore-ocsp-service-url

Ignore all OCSP URLs contained in the certificate. The effect is to force the use of the default responder.

--honor-http-proxy

If the environment variable `http_proxy` has been set, use its value to access HTTP servers.

--http-proxy *host*[:*port*]

Use *host* and *port* to access HTTP servers. The use of this option overrides the environment variable `http_proxy` regardless whether ‘--honor-http-proxy’ has been set.

--ldap-proxy *host*[:*port*]

Use *host* and *port* to connect to LDAP servers. If *port* is omitted, port 389 (standard LDAP port) is used. This overrides any specified host and port part in a LDAP URL and will also be used if host and port have been omitted from the URL.

--only-ldap-proxy

Never use anything else but the LDAP "proxy" as configured with '**--ldap-proxy**'. Usually **dirmngr** tries to use other configured LDAP server if the connection using the "proxy" failed.

--ldapservlist-file *file*

Read the list of LDAP servers to consult for CRLs and certificates from *file* instead of the default per-user ldap server list file. The default value for *file* is '**dirmngr_ldapservers.conf**'.

This server list file contains one LDAP server per line in the format

HOSTNAME:PORT:USERNAME:PASSWORD:BASE_DN

Lines starting with a '#' are comments.

Note that as usual all strings entered are expected to be UTF-8 encoded. Obviously this will lead to problems if the password has originally been encoded as Latin-1. There is no other solution here than to put such a password in the binary encoding into the file (i.e. non-ascii characters won't show up readable).¹

--ldaptimeout *secs*

Specify the number of seconds to wait for an LDAP query before timing out. The default are 15 seconds. 0 will never timeout.

--add-servers

This option makes **dirmngr** add any servers it discovers when validating certificates against CRLs to the internal list of servers to consult for certificates and CRLs.

This option is useful when trying to validate a certificate that has a CRL distribution point that points to a server that is not already listed in the **ldapservlist**. **Dirmngr** will always go to this server and try to download the CRL, but chances are high that the certificate used to sign the CRL is located on the same server. So if **dirmngr** doesn't add that new server to list, it will often not be able to verify the signature of the CRL unless the **--add-servers** option is used.

Note: The current version of **dirmngr** has this option disabled by default.

--allow-ocsp

This option enables OCSP support if requested by the client.

OCSP requests are rejected by default because they may violate the privacy of the user; for example it is possible to track the time when a user is reading a mail.

--ocsp-responder *url*

Use *url* as the default OCSP Responder if the certificate does not contain information about an assigned responder. Note, that **--ocsp-signer** must also be set to a valid certificate.

¹ The **gpgconf** tool might be helpful for frontends as it enables editing this configuration file using percent-escaped strings.

--ocsp-signer *fpr* | *file*

Use the certificate with the fingerprint *fpr* to check the responses of the default OCSP Responder. Alternatively a filename can be given in which case the response is expected to be signed by one of the certificates described in that file. Any argument which contains a slash, dot or tilde is considered a filename. Usual filename expansion takes place: A tilde at the start followed by a slash is replaced by the content of `HOME`, no slash at start describes a relative filename which will be searched at the home directory. To make sure that the *file* is searched in the home directory, either prepend the name with `"/` or use a name which contains a dot.

If a response has been signed by a certificate described by these fingerprints no further check upon the validity of this certificate is done.

The format of the *FILE* is a list of SHA-1 fingerprint, one per line with optional colons between the bytes. Empty lines and lines prefix with a hash mark are ignored.

--ocsp-max-clock-skew *n*

The number of seconds a skew between the OCSP responder and them local clock is accepted. Default is 600 (10 minutes).

--ocsp-max-period *n*

Seconds a response is at maximum considered valid after the time given in the `thisUpdate` field. Default is 7776000 (90 days).

--ocsp-current-period *n*

The number of seconds an OCSP response is considered valid after the time given in the `NEXT_UPDATE` datum. Default is 10800 (3 hours).

--max-replies *n*

Do not return more that *n* items in one query. The default is 10.

--ignore-cert-extension *oid*

Add *oid* to the list of ignored certificate extensions. The *oid* is expected to be in dotted decimal form, like `2.5.29.3`. This option may be used more than once. Critical flagged certificate extensions matching one of the OIDs in the list are treated as if they are actually handled and thus the certificate won't be rejected due to an unknown critical extension. Use this option with care because extensions are usually flagged as critical for a reason.

--hkp-cacert *file*

Use the root certificates in *file* for verification of the TLS certificates used with `hkps` (keyserver access over TLS). If the file is in PEM format a suffix of `.pem` is expected for *file*. This option may be given multiple times to add more root certificates. Tilde expansion is supported.

If no `hkp-cacert` directive is present, `dirmngr` will make a reasonable choice: if the keyserver in question is the special pool `hkps.pool.sks-keyservers.net`, it will use the bundled root certificate for that pool. Otherwise, it will use the system CAs.

3.3 Configuration

Dirmngr makes use of several directories when running in daemon mode: There are a few configuration files which control the operation of dirmngr. By default they may all be found in the current home directory (see [option `-homedir`], page 4).

`'dirmngr.conf'`

This is the standard configuration file read by dirmngr on startup. It may contain any valid long option; the leading two dashes may not be entered and the option may not be abbreviated. This file is also read after a SIGHUP however not all options will actually have an effect. This default name may be changed on the command line (see [option `-options`], page 4). You should backup this file.

`'/etc/gnupg/trusted-certs'`

This directory should be filled with certificates of Root CAs you are trusting in checking the CRLs and signing OCSF Responses.

Usually these are the same certificates you use with the applications making use of dirmngr. It is expected that each of these certificate files contain exactly one DER encoded certificate in a file with the suffix `'.crt'` or `'.der'`. dirmngr reads those certificates on startup and when given a SIGHUP. Certificates which are not readable or do not make up a proper X.509 certificate are ignored; see the log file for details.

Applications using dirmngr (e.g. gpgsm) can request these certificates to complete a trust chain in the same way as with the extra-certs directory (see below).

Note that for OCSF responses the certificate specified using the option `'--ocsp-signer'` is always considered valid to sign OCSF requests.

`'/etc/gnupg/extra-certs'`

This directory may contain extra certificates which are preloaded into the internal cache on startup. Applications using dirmngr (e.g. gpgsm) can request cached certificates to complete a trust chain. This is convenient in cases you have a couple intermediate CA certificates or certificates usually used to sign OCSF responses. These certificates are first tried before going out to the net to look for them. These certificates must also be DER encoded and suffixed with `'.crt'` or `'.der'`.

`'~/ .gnupg/crls.d'`

This directory is used to store cached CRLs. The `'crls.d'` part will be created by dirmngr if it does not exist but you need to make sure that the upper directory exists.

To be able to see what's going on you should create the configure file `'~/gnupg/dirmngr.conf'` with at least one line:

```
log-file ~/dirmngr.log
```

To be able to perform OCSF requests you probably want to add the line:

```
allow-ocsp
```

To make sure that new options are read and that after the installation of a new GnuPG version the installed dirmngr is running, you may want to kill an existing dirmngr first:


```
gpgconf --kill dirmngr
```

You may check the log file to see whether all desired root certificates have been loaded correctly.

3.4 Use of signals

A running `dirmngr` may be controlled by signals, i.e. using the `kill` command to send a signal to the process.

Here is a list of supported signals:

SIGHUP This signal flushes all internally cached CRLs as well as any cached certificates. Then the certificate cache is reinitialized as on startup. Options are re-read from the configuration file. Instead of sending this signal it is better to use

```
gpgconf --reload dirmngr
```

SIGTERM Shuts down the process but waits until all current requests are fulfilled. If the process has received 3 of these signals and requests are still pending, a shutdown is forced. You may also use

```
gpgconf --kill dirmngr
```

instead of this signal

SIGINT Shuts down the process immediately.

SIGUSR1 This prints some caching statistics to the log file.

3.5 Examples

Here is an example on how to show `dirmngr`'s internal table of OpenPGP keyserver addresses. The output is intended for debugging purposes and not part of a defined API.

```
gpg-connect-agent --dirmngr 'keyserver --hosttable' /bye
```

To inhibit the use of a particular host you have noticed in one of the keyserver pools, you may use

```
gpg-connect-agent --dirmngr 'keyserver --dead pgpkeys.bnd.de' /bye
```

The description of the `keyserver` command can be printed using

```
gpg-connect-agent --dirmngr 'help keyserver' /bye
```

3.6 Dirmngr's Assuan Protocol

Assuan is the IPC protocol used to access `dirmngr`. This is a description of the commands implemented by `dirmngr`.

3.6.1 Return the certificate(s) found

Lookup certificate. To allow multiple patterns (which are ORed) quoting is required: Spaces are to be translated into `+` or into `%20`; obviously this requires that the usual escape quoting rules are applied. The server responds with:

```
S: D <DER encoded certificate>
S: END
S: D <second DER encoded certificate>
```

```
S: END
S: OK
```

In this example 2 certificates are returned. The server may return any number of certificates; OK will also be returned when no certificates were found. The `dirmngr` might return a status line

```
S: S TRUNCATED <n>
```

To indicate that the output was truncated to N items due to a limitation of the server or by an arbitrary set limit.

The option ‘`--url`’ may be used if instead of a search pattern a complete URL to the certificate is known:

```
C: LOOKUP --url CN%3DWerner%20Koch,o%3DIntevation%20GmbH,c%3DDE?userCertificate
```

If the option ‘`--cache-only`’ is given, no external lookup is done so that only certificates from the cache are returned.

With the option ‘`--single`’, the first and only the first match will be returned. Unless option ‘`--cache-only`’ is also used, no local lookup will be done in this case.

3.6.2 Validate a certificate using a CRL or OCSP

```
ISVALID [--only-ocsp] [--force-default-responder] certid|certfpr
```

Check whether the certificate described by the *certid* has been revoked. Due to caching, the `Dirmngr` is able to answer immediately in most cases.

The *certid* is a hex encoded string consisting of two parts, delimited by a single dot. The first part is the SHA-1 hash of the issuer name and the second part the serial number.

Alternatively the certificate’s SHA-1 fingerprint *certfpr* may be given in which case an OCSP request is done before consulting the CRL. If the option ‘`--only-ocsp`’ is given, no fallback to a CRL check will be used. If the option ‘`--force-default-responder`’ is given, only the default OCSP responder will be used and any other methods of obtaining an OCSP responder URL won’t be used.

Common return values are:

GPG_ERR_NO_ERROR (0)

This is the positive answer: The certificate is not revoked and we have an up-to-date revocation list for that certificate. If OCSP was used the responder confirmed that the certificate has not been revoked.

GPG_ERR_CERT_REVOKED

This is the negative answer: The certificate has been revoked. Either it is in a CRL and that list is up to date or an OCSP responder informed us that it has been revoked.

GPG_ERR_NO_CRL_KNOWN

No CRL is known for this certificate or the CRL is not valid or out of date.

GPG_ERR_NO_DATA

The OCSP responder returned an “unknown” status. This means that it is not aware of the certificate’s status.

GPG_ERR_NOT_SUPPORTED

This is commonly seen if OSCP support has not been enabled in the configuration.

If DirMngr has not enough information about the given certificate (which is the case for not yet cached certificates), it will inquire the missing data:

```
S: INQUIRE SENDCERT <CertID>
C: D <DER encoded certificate>
C: END
```

A client should be aware that DirMngr may ask for more than one certificate.

If Dirmngr has a certificate but the signature of the certificate could not be validated because the root certificate is not known to dirmngr as trusted, it may ask back to see whether the client trusts this the root certificate:

```
S: INQUIRE ISTRUSTED <CertHexfpr>
C: D 1
C: END
```

Only this answer will let Dirmngr consider the certificate as valid.

3.6.3 Validate a certificate using a CRL

Check whether the certificate with FINGERPRINT (SHA-1 hash of the entire X.509 certificate blob) is valid or not by consulting the CRL responsible for this certificate. If the fingerprint has not been given or the certificate is not known, the function inquires the certificate using:

```
S: INQUIRE TARGETCERT
C: D <DER encoded certificate>
C: END
```

Thus the caller is expected to return the certificate for the request (which should match FINGERPRINT) as a binary blob. Processing then takes place without further interaction; in particular dirmngr tries to locate other required certificate by its own mechanism which includes a local certificate store as well as a list of trusted root certificates.

The return code is 0 for success; i.e. the certificate has not been revoked or one of the usual error codes from libgpg-error.

3.6.4 Validate a certificate using OSCP

```
CHECKOCSP [--force-default-responder] [fingerprint]
```

Check whether the certificate with *fingerprint* (the SHA-1 hash of the entire X.509 certificate blob) is valid by consulting the appropriate OSCP responder. If the fingerprint has not been given or the certificate is not known by Dirmngr, the function inquires the certificate using:

```
S: INQUIRE TARGETCERT
C: D <DER encoded certificate>
C: END
```

Thus the caller is expected to return the certificate for the request (which should match *fingerprint*) as a binary blob. Processing then takes place without further interaction; in

particular dirmngr tries to locate other required certificates by its own mechanism which includes a local certificate store as well as a list of trusted root certificates.

If the option ‘`--force-default-responder`’ is given, only the default OCS responder is used. This option is the per-command variant of the global option ‘`--ignore-ocsp-service-url`’.

The return code is 0 for success; i.e. the certificate has not been revoked or one of the usual error codes from libgpg-error.

3.6.5 Put a certificate into the internal cache

Put a certificate into the internal cache. This command might be useful if a client knows in advance certificates required for a test and wants to make sure they get added to the internal cache. It is also helpful for debugging. To get the actual certificate, this command immediately inquires it using

```
S: INQUIRE TARGETCERT
C: D <DER encoded certificate>
C: END
```

Thus the caller is expected to return the certificate for the request as a binary blob.

The return code is 0 for success; i.e. the certificate has not been successfully cached or one of the usual error codes from libgpg-error.

3.6.6 Validate a certificate for debugging

Validate a certificate using the certificate validation function used internally by dirmngr. This command is only useful for debugging. To get the actual certificate, this command immediately inquires it using

```
S: INQUIRE TARGETCERT
C: D <DER encoded certificate>
C: END
```

Thus the caller is expected to return the certificate for the request as a binary blob.

4 Invoking GPG

gpg2 is the OpenPGP part of the GNU Privacy Guard (GnuPG). It is a tool to provide digital encryption and signing services using the OpenPGP standard. **gpg2** features complete key management and all the bells and whistles you would expect from a full OpenPGP implementation.

There are two main versions of GnuPG: GnuPG 1.x and GnuPG 2.x. GnuPG 2.x supports modern encryption algorithms and thus should be preferred over GnuPG 1.x. You only need to use GnuPG 1.x if your platform doesn't support GnuPG 2.x, or you need support for some features that GnuPG 2.x has deprecated, e.g., decrypting data created with PGP-2 keys.

In contrast to the standalone command **gpg** from GnuPG 1.x, the 2.x version is commonly installed under the name **gpg2**.

See [Option Index], page 197, for an index to **gpg2**'s commands and options.

4.1 Commands

Commands are not distinguished from options except for the fact that only one command is allowed. Generally speaking, irrelevant options are silently ignored, and may not be checked for correctness.

gpg2 may be run with no commands. In this case it will print a warning perform a reasonable action depending on the type of file it is given as input (an encrypted message is decrypted, a signature is verified, a file containing keys is listed, etc.).

If you run into any problems, please add the option '**--verbose**' to the invocation to see more diagnostics.

4.1.1 Commands not specific to the function

- version**
Print the program version and licensing information. Note that you cannot abbreviate this command.
- help**
- h**
Print a usage message summarizing the most useful command-line options. Note that you cannot arbitrarily abbreviate this command (though you can use its short form '**-h**').
- warranty**
Print warranty information.
- dump-options**
Print a list of all available options and commands. Note that you cannot abbreviate this command.

4.1.2 Commands to select the type of operation

- sign**
- s**
Sign a message. This command may be combined with '**--encrypt**' (to sign and encrypt a message), '**--symmetric**' (to sign and symmetrically encrypt

a message), or both ‘`--encrypt`’ and ‘`--symmetric`’ (to sign and encrypt a message that can be decrypted using a secret key or a passphrase). The signing key is chosen by default or can be set explicitly using the ‘`--local-user`’ and ‘`--default-key`’ options.

`--clear-sign`

`--clearsign`

Make a cleartext signature. The content in a cleartext signature is readable without any special software. OpenPGP software is only needed to verify the signature. cleartext signatures may modify end-of-line whitespace for platform independence and are not intended to be reversible. The signing key is chosen by default or can be set explicitly using the ‘`--local-user`’ and ‘`--default-key`’ options.

`--detach-sign`

`-b` Make a detached signature.

`--encrypt`

`-e` Encrypt data to one or more public keys. This command may be combined with ‘`--sign`’ (to sign and encrypt a message), ‘`--symmetric`’ (to encrypt a message that can be decrypted using a secret key or a passphrase), or ‘`--sign`’ and ‘`--symmetric`’ together (for a signed message that can be decrypted using a secret key or a passphrase). ‘`--recipient`’ and related options specify which public keys to use for encryption.

`--symmetric`

`-c` Encrypt with a symmetric cipher using a passphrase. The default symmetric cipher used is AES-128, but may be chosen with the ‘`--cipher-algo`’ option. This command may be combined with ‘`--sign`’ (for a signed and symmetrically encrypted message), ‘`--encrypt`’ (for a message that may be decrypted via a secret key or a passphrase), or ‘`--sign`’ and ‘`--encrypt`’ together (for a signed message that may be decrypted via a secret key or a passphrase). `gpg2` caches the passphrase used for symmetric encryption so that a decrypt operation may not require that the user needs to enter the passphrase. The option ‘`--no-symkey-cache`’ can be used to disable this feature.

`--store` Store only (make a simple literal data packet).

`--decrypt`

`-d` Decrypt the file given on the command line (or STDIN if no file is specified) and write it to STDOUT (or the file specified with ‘`--output`’). If the decrypted file is signed, the signature is also verified. This command differs from the default operation, as it never writes to the filename which is included in the file and it rejects files that don’t begin with an encrypted message.

`--verify` Assume that the first argument is a signed file and verify it without generating any output. With no arguments, the signature packet is read from STDIN. If only one argument is given, the specified file is expected to include a complete signature.

With more than one argument, the first argument should specify a file with a detached signature and the remaining files should contain the signed data. To

read the signed data from STDIN, use ‘-’ as the second filename. For security reasons, a detached signature will not read the signed material from STDIN if not explicitly specified.

Note: If the option ‘--batch’ is not used, **gpg2** may assume that a single argument is a file with a detached signature, and it will try to find a matching data file by stripping certain suffixes. Using this historical feature to verify a detached signature is strongly discouraged; you should always specify the data file explicitly.

Note: When verifying a cleartext signature, **gpg2** verifies only what makes up the cleartext signed data and not any extra data outside of the cleartext signature or the header lines directly following the dash marker line. The option **--output** may be used to write out the actual signed data, but there are other pitfalls with this format as well. It is suggested to avoid cleartext signatures in favor of detached signatures.

Note: Sometimes the use of the **gpgv** tool is easier than using the full-fledged **gpg** with this option. **gpgv** is designed to compare signed data against a list of trusted keys and returns with success only for a good signature. It has its own manual page.

--multifile

This modifies certain other commands to accept multiple files for processing on the command line or read from STDIN with each filename on a separate line. This allows for many files to be processed at once. ‘--multifile’ may currently be used along with ‘--verify’, ‘--encrypt’, and ‘--decrypt’. Note that ‘--multifile --verify’ may not be used with detached signatures.

--verify-files

Identical to ‘--multifile --verify’.

--encrypt-files

Identical to ‘--multifile --encrypt’.

--decrypt-files

Identical to ‘--multifile --decrypt’.

--list-keys

-k

--list-public-keys

List the specified keys. If no keys are specified, then all keys from the configured public keyrings are listed.

Never use the output of this command in scripts or other programs. The output is intended only for humans and its format is likely to change. The ‘--with-colons’ option emits the output in a stable, machine-parseable format, which is intended for use by scripts and other programs.

--list-secret-keys

-K

List the specified secret keys. If no keys are specified, then all known secret keys are listed. A # after the initial tags **sec** or **ssb** means that the secret key or subkey is currently not usable. We also say that this key has been taken offline

(for example, a primary key can be taken offline by exporting the key using the command '`--export-secret-subkeys`'). A `>` after these tags indicate that the key is stored on a smartcard. See also '`--list-keys`'.

`--check-signatures`

`--check-sigs`

Same as '`--list-keys`', but the key signatures are verified and listed too. Note that for performance reasons the revocation status of a signing key is not shown. This command has the same effect as using '`--list-keys`' with '`--with-sig-check`'.

The status of the verification is indicated by a flag directly following the "sig" tag (and thus before the flags described below. A "!" indicates that the signature has been successfully verified, a "-" denotes a bad signature and a "%" is used if an error occurred while checking the signature (e.g. a non supported algorithm). Signatures where the public key is not available are not listed; to see their keyids the command '`--list-sigs`' can be used.

For each signature listed, there are several flags in between the signature status flag and keyid. These flags give additional information about each key signature. From left to right, they are the numbers 1-3 for certificate check level (see '`--ask-cert-level`'), "L" for a local or non-exportable signature (see '`--lsign-key`'), "R" for a nonRevocable signature (see the '`--edit-key`' command "nrsign"), "P" for a signature that contains a policy URL (see '`--cert-policy-url`'), "N" for a signature that contains a notation (see '`--cert-notation`'), "X" for an eXpired signature (see '`--ask-cert-expire`'), and the numbers 1-9 or "T" for 10 and above to indicate trust signature levels (see the '`--edit-key`' command "tsign").

`--locate-keys`

`--locate-external-keys`

Locate the keys given as arguments. This command basically uses the same algorithm as used when locating keys for encryption or signing and may thus be used to see what keys `gpg2` might use. In particular external methods as defined by '`--auto-key-locate`' may be used to locate a key. Only public keys are listed. The variant '`--locate-external-keys`' does not consider a locally existing key and can thus be used to force the refresh of a key via the defined external methods.

`--show-keys`

This command takes OpenPGP keys as input and prints information about them in the same way the command '`--list-keys`' does for locally stored key. In addition the list options `show-unusable-uids`, `show-unusable-subkeys`, `show-notations` and `show-policy-urls` are also enabled. As usual for automated processing, this command should be combined with the option '`--with-colons`'.

`--fingerprint`

List all keys (or the specified ones) along with their fingerprints. This is the same output as '`--list-keys`' but with the additional output of a line with the fingerprint. May also be combined with '`--check-signatures`'. If this

command is given twice, the fingerprints of all secondary keys are listed too. This command also forces pretty printing of fingerprints if the keyid format has been set to "none".

--list-packets

List only the sequence of packets. This command is only useful for debugging. When used with option '**--verbose**' the actual MPI values are dumped and not only their lengths. Note that the output of this command may change with new releases.

--edit-card

--card-edit

Present a menu to work with a smartcard. The subcommand "help" provides an overview on available commands. For a detailed description, please see the Card HOWTO at <https://gnupg.org/documentation/howtos.html#GnuPG-cardHOWTO> .

--card-status

Show the content of the smart card.

--change-pin

Present a menu to allow changing the PIN of a smartcard. This functionality is also available as the subcommand "passwd" with the '**--edit-card**' command.

--delete-keys name

Remove key from the public keyring. In batch mode either '**--yes**' is required or the key must be specified by fingerprint. This is a safeguard against accidental deletion of multiple keys. If the exclamation mark syntax is used with the fingerprint of a subkey only that subkey is deleted; if the exclamation mark is used with the fingerprint of the primary key the entire public key is deleted.

--delete-secret-keys name

Remove key from the secret keyring. In batch mode the key must be specified by fingerprint. The option '**--yes**' can be used to advise gpg-agent not to request a confirmation. This extra pre-caution is done because **gpg2** can't be sure that the secret key (as controlled by gpg-agent) is only used for the given OpenPGP public key. If the exclamation mark syntax is used with the fingerprint of a subkey only the secret part of that subkey is deleted; if the exclamation mark is used with the fingerprint of the primary key only the secret part of the primary key is deleted.

--delete-secret-and-public-key name

Same as '**--delete-key**', but if a secret key exists, it will be removed first. In batch mode the key must be specified by fingerprint. The option '**--yes**' can be used to advise gpg-agent not to request a confirmation.

--export

Either export all keys from all keyrings (default keyrings and those registered via option '**--keyring**'), or if at least one name is given, those of the given name. The exported keys are written to STDOUT or to the file given with option '**--output**'. Use together with '**--armor**' to mail those keys.

--send-keys *keyIDs*

Similar to ‘--export’ but sends the keys to a keyserver. Fingerprints may be used instead of key IDs. Don’t send your complete keyring to a keyserver — select only those keys which are new or changed by you. If no *keyIDs* are given, **gpg2** does nothing.

Take care: Keyservers are by design write only systems and thus it is not possible to ever delete keys once they have been send to a keyserver.

--export-secret-keys**--export-secret-subkeys**

Same as ‘--export’, but exports the secret keys instead. The exported keys are written to STDOUT or to the file given with option ‘--output’. This command is often used along with the option ‘--armor’ to allow for easy printing of the key for paper backup; however the external tool **paperkey** does a better job of creating backups on paper. Note that exporting a secret key can be a security risk if the exported keys are sent over an insecure channel.

The second form of the command has the special property to render the secret part of the primary key useless; this is a GNU extension to OpenPGP and other implementations can not be expected to successfully import such a key. Its intended use is in generating a full key with an additional signing subkey on a dedicated machine. This command then exports the key without the primary key to the main machine.

GnuPG may ask you to enter the passphrase for the key. This is required, because the internal protection method of the secret key is different from the one specified by the OpenPGP protocol.

--export-ssh-key

This command is used to export a key in the OpenSSH public key format. It requires the specification of one key by the usual means and exports the latest valid subkey which has an authentication capability to STDOUT or to the file given with option ‘--output’. That output can directly be added to ssh’s ‘*authorized_key*’ file.

By specifying the key to export using a key ID or a fingerprint suffixed with an exclamation mark (!), a specific subkey or the primary key can be exported. This does not even require that the key has the authentication capability flag set.

--import**--fast-import**

Import/merge keys. This adds the given keys to the keyring. The fast version is currently just a synonym.

There are a few other options which control how this command works. Most notable here is the ‘--import-options *merge-only*’ option which does not insert new keys but does only the merging of new signatures, user-IDs and subkeys.

--receive-keys *keyIDs***--recv-keys *keyIDs***

Import the keys with the given *keyIDs* from a keyserver.

--refresh-keys

Request updates from a keyserver for keys that already exist on the local keyring. This is useful for updating a key with the latest signatures, user IDs, etc. Calling this with no arguments will refresh the entire keyring.

--search-keys *names*

Search the keyserver for the given *names*. Multiple names given here will be joined together to create the search string for the keyserver. Note that keyservers search for *names* in a different and simpler way than gpg does. The best choice is to use a mail address. Due to data privacy reasons keyservers may even not even allow searching by user id or mail address and thus may only return results when being used with the ‘--recv-key’ command to search by key fingerprint or keyid.

--fetch-keys *URIs*

Retrieve keys located at the specified *URIs*. Note that different installations of GnuPG may support different protocols (HTTP, FTP, LDAP, etc.). When using HTTPS the system provided root certificates are used by this command.

--update-trustdb

Do trust database maintenance. This command iterates over all keys and builds the Web of Trust. This is an interactive command because it may have to ask for the "ownertrust" values for keys. The user has to give an estimation of how far she trusts the owner of the displayed key to correctly certify (sign) other keys. GnuPG only asks for the ownertrust value if it has not yet been assigned to a key. Using the ‘--edit-key’ menu, the assigned value can be changed at any time.

--check-trustdb

Do trust database maintenance without user interaction. From time to time the trust database must be updated so that expired keys or signatures and the resulting changes in the Web of Trust can be tracked. Normally, GnuPG will calculate when this is required and do it automatically unless ‘--no-auto-check-trustdb’ is set. This command can be used to force a trust database check at any time. The processing is identical to that of ‘--update-trustdb’ but it skips keys with a not yet defined "ownertrust".

For use with cron jobs, this command can be used together with ‘--batch’ in which case the trust database check is done only if a check is needed. To force a run even in batch mode add the option ‘--yes’.

--export-ownertrust

Send the ownertrust values to STDOUT. This is useful for backup purposes as these values are the only ones which can’t be re-created from a corrupted trustdb. Example:

```
gpg2
--export-ownertrust > otrust.txt
```

--import-ownertrust

Update the trustdb with the ownertrust values stored in *files* (or STDIN if not given); existing values will be overwritten. In case of a severely damaged

trustdb and if you have a recent backup of the ownertrust values (e.g. in the file ‘otrust.txt’), you may re-create the trustdb using these commands:

```
cd ~/.gnupg
rm trustdb.gpg
gpg2
--import-ownertrust < otrust.txt
```

--rebuild-keydb-caches

When updating from version 1.0.6 to 1.0.7 this command should be used to create signature caches in the keyring. It might be handy in other situations too.

--print-md *algo*

--print-mds

Print message digest of algorithm *algo* for all given files or STDIN. With the second form (or a deprecated "*" for *algo*) digests for all available algorithms are printed.

--gen-random 0|1|2 *count*

Emit *count* random bytes of the given quality level 0, 1 or 2. If *count* is not given or zero, an endless sequence of random bytes will be emitted. If used with ‘--armor’ the output will be base64 encoded. PLEASE, don’t use this command unless you know what you are doing; it may remove precious entropy from the system!

--gen-prime *mode bits*

Use the source, Luke :-). The output format is subject to change with ant release.

--enarmor

--dearmor

Pack or unpack an arbitrary input into/from an OpenPGP ASCII armor. This is a GnuPG extension to OpenPGP and in general not very useful.

--tofu-policy {auto|good|unknown|bad|ask} *keys*

Set the TOFU policy for all the bindings associated with the specified *keys*. For more information about the meaning of the policies, see [\[trust-model-tofu\]](#), [page 57](#). The *keys* may be specified either by their fingerprint (preferred) or their keyid.

4.1.3 How to manage your keys

This section explains the main commands for key management.

--quick-generate-key *user-id* [*algo*] [*usage*] [*expire*]]

--quick-gen-key

This is a simple command to generate a standard key with one user id. In contrast to ‘--generate-key’ the key is generated directly without the need to answer a bunch of prompts. Unless the option ‘--yes’ is given, the key creation will be canceled if the given user id already exists in the keyring.

If invoked directly on the console without any special options an answer to a “Continue?” style confirmation prompt is required. In case the user id already

exists in the keyring a second prompt to force the creation of the key will show up.

If *algo* or *usage* are given, only the primary key is created and no prompts are shown. To specify an expiration date but still create a primary and subkey use “default” or “future-default” for *algo* and “default” for *usage*. For a description of these optional arguments see the command `--quick-add-key`. The *usage* accepts also the value “cert” which can be used to create a certification only primary key; the default is to create certification and signing key.

The *expire* argument can be used to specify an expiration date for the key. Several formats are supported; commonly the ISO formats “YYYY-MM-DD” or “YYYYMMDDThhmmss” are used. To make the key expire in N seconds, N days, N weeks, N months, or N years use “seconds=N”, “Nd”, “Nw”, “Nm”, or “Ny” respectively. Not specifying a value, or using “-” results in a key expiring in a reasonable default interval. The values “never”, “none” can be used for no expiration date.

If this command is used with ‘`--batch`’, ‘`--pinentry-mode`’ has been set to `loopback`, and one of the passphrase options (‘`--passphrase`’, ‘`--passphrase-fd`’, or ‘`passphrase-file`’) is used, the supplied passphrase is used for the new key and the agent does not ask for it. To create a key without any protection `--passphrase ''` may be used.

To create an OpenPGP key from the keys available on the currently inserted smartcard, the special string “card” can be used for *algo*. If the card features an encryption and a signing key, gpg will figure them out and creates an OpenPGP key consisting of the usual primary key and one subkey. This works only with certain smartcards. Note that the interactive ‘`--full-gen-key`’ command allows to do the same but with greater flexibility in the selection of the smartcard keys.

Note that it is possible to create a primary key and a subkey using non-default algorithms by using “default” and changing the default parameters using the option ‘`--default-new-key-algo`’.

`--quick-set-expire fpr expire [*|subfprs]`

With two arguments given, directly set the expiration time of the primary key identified by *fpr* to *expire*. To remove the expiration time 0 can be used. With three arguments and the third given as an asterisk, the expiration time of all non-revoked and not yet expired subkeys are set to *expire*. With more than two arguments and a list of fingerprints given for *subfprs*, all non-revoked subkeys matching these fingerprints are set to *expire*.

`--quick-add-key fpr [algo [usage [expire]]]`

Directly add a subkey to the key identified by the fingerprint *fpr*. Without the optional arguments an encryption subkey is added. If any of the arguments are given a more specific subkey is added.

algo may be any of the supported algorithms or curve names given in the format as used by key listings. To use the default algorithm the string “default” or “-” can be used. Supported algorithms are “rsa”, “dsa”, “elg”, “ed25519”, “cv25519”, and other ECC curves. For example the string “rsa” adds an RSA

key with the default key length; a string “rsa4096” requests that the key length is 4096 bits. The string “future-default” is an alias for the algorithm which will likely be used as default algorithm in future versions of gpg. To list the supported ECC curves the command `gpg --with-colons --list-config curve` can be used.

Depending on the given *algo* the subkey may either be an encryption subkey or a signing subkey. If an algorithm is capable of signing and encryption and such a subkey is desired, a *usage* string must be given. This string is either “default” or “-” to keep the default or a comma delimited list (or space delimited list) of keywords: “sign” for a signing subkey, “auth” for an authentication subkey, and “encr” for an encryption subkey (“encrypt” can be used as alias for “encr”). The valid combinations depend on the algorithm.

The *expire* argument can be used to specify an expiration date for the key. Several formats are supported; commonly the ISO formats “YYYY-MM-DD” or “YYYYMMDDThhmmss” are used. To make the key expire in N seconds, N days, N weeks, N months, or N years use “seconds=N”, “Nd”, “Nw”, “Nm”, or “Ny” respectively. Not specifying a value, or using “-” results in a key expiring in a reasonable default interval. The values “never”, “none” can be used for no expiration date.

`--generate-key`

`--gen-key`

Generate a new key pair using the current default parameters. This is the standard command to create a new key. In addition to the key a revocation certificate is created and stored in the ‘`openpgp-revocs.d`’ directory below the GnuPG home directory.

`--full-generate-key`

`--full-gen-key`

Generate a new key pair with dialogs for all options. This is an extended version of ‘`--generate-key`’.

There is also a feature which allows you to create keys in batch mode. See the manual section “Unattended key generation” on how to use this.

`--generate-revocation name`

`--gen-revoke name`

Generate a revocation certificate for the complete key. To only revoke a subkey or a key signature, use the ‘`--edit`’ command.

This command merely creates the revocation certificate so that it can be used to revoke the key if that is ever needed. To actually revoke a key the created revocation certificate needs to be merged with the key to revoke. This is done by importing the revocation certificate using the ‘`--import`’ command. Then the revoked key needs to be published, which is best done by sending the key to a keyserver (command ‘`--send-key`’) and by exporting (‘`--export`’) it to a file which is then send to frequent communication partners.

--generate-designated-revocation *name*

--desig-revoke *name*

Generate a designated revocation certificate for a key. This allows a user (with the permission of the keyholder) to revoke someone else's key.

--edit-key

Present a menu which enables you to do most of the key management related tasks. It expects the specification of a key on the command line.

uid *n* Toggle selection of user ID or photographic user ID with index *n*. Use * to select all and 0 to deselect all.

key *n* Toggle selection of subkey with index *n* or key ID *n*. Use * to select all and 0 to deselect all.

sign Make a signature on key of user **name**. If the key is not yet signed by the default user (or the users given with '-u'), the program displays the information of the key again, together with its fingerprint and asks whether it should be signed. This question is repeated for all users specified with '-u'.

lsign Same as "sign" but the signature is marked as non-exportable and will therefore never be used by others. This may be used to make keys valid only in the local environment.

nrsign Same as "sign" but the signature is marked as non-revocable and can therefore never be revoked.

tsign Make a trust signature. This is a signature that combines the notions of certification (like a regular signature), and trust (like the "trust" command). It is generally only useful in distinct communities or groups. For more information please read the sections "Trust Signature" and "Regular Expression" in RFC-4880.

Note that "l" (for local / non-exportable), "nr" (for non-revocable, and "t" (for trust) may be freely mixed and prefixed to "sign" to create a signature of any type desired.

If the option '**--only-sign-text-ids**' is specified, then any non-text based user ids (e.g., photo IDs) will not be selected for signing.

delsig Delete a signature. Note that it is not possible to retract a signature, once it has been sent to the public (i.e. to a keyserver). In that case you better use **revsig**.

revsig Revoke a signature. For every signature which has been generated by one of the secret keys, GnuPG asks whether a revocation certificate should be generated.

check Check the signatures on all selected user IDs. With the extra option **selfsig** only self-signatures are shown.

adduid Create an additional user ID.

- addphoto** Create a photographic user ID. This will prompt for a JPEG file that will be embedded into the user ID. Note that a very large JPEG will make for a very large key. Also note that some programs will display your JPEG unchanged (GnuPG), and some programs will scale it to fit in a dialog box (PGP).
- showphoto** Display the selected photographic user ID.
- deluid** Delete a user ID or photographic user ID. Note that it is not possible to retract a user id, once it has been send to the public (i.e. to a keyserver). In that case you better use **revuid**.
- revuid** Revoke a user ID or photographic user ID.
- primary** Flag the current user id as the primary one, removes the primary user id flag from all other user ids and sets the timestamp of all affected self-signatures one second ahead. Note that setting a photo user ID as primary makes it primary over other photo user IDs, and setting a regular user ID as primary makes it primary over other regular user IDs.
- keyserver** Set a preferred keyserver for the specified user ID(s). This allows other users to know where you prefer they get your key from. See '**--keyserver-options honor-keyserver-url**' for more on how this works. Setting a value of "none" removes an existing preferred keyserver.
- notation** Set a name=value notation for the specified user ID(s). See '**--cert-notation**' for more on how this works. Setting a value of "none" removes all notations, setting a notation prefixed with a minus sign (-) removes that notation, and setting a notation name (without the =value) prefixed with a minus sign removes all notations with that name.
- pref** List preferences from the selected user ID. This shows the actual preferences, without including any implied preferences.
- showpref** More verbose preferences listing for the selected user ID. This shows the preferences in effect by including the implied preferences of 3DES (cipher), SHA-1 (digest), and Uncompressed (compression) if they are not already included in the preference list. In addition, the preferred keyserver and signature notations (if any) are shown.
- setpref *string*** Set the list of user ID preferences to *string* for all (or just the selected) user IDs. Calling setpref with no arguments sets the preference list to the default (either built-in or set via '**--default-preference-list**'), and calling setpref with "none" as the argument sets an empty preference list. Use **gpg2--version** to get a list of available algorithms. Note that while you can change the preferences on an attribute user ID (aka "photo ID"),

GnuPG does not select keys via attribute user IDs so these preferences will not be used by GnuPG.

When setting preferences, you should list the algorithms in the order which you'd like to see them used by someone else when encrypting a message to your key. If you don't include 3DES, it will be automatically added at the end. Note that there are many factors that go into choosing an algorithm (for example, your key may not be the only recipient), and so the remote OpenPGP application being used to send to you may or may not follow your exact chosen order for a given message. It will, however, only choose an algorithm that is present on the preference list of every recipient key. See also the INTEROPERABILITY WITH OTHER OPENPGP PROGRAMS section below.

addkey	Add a subkey to this key.
addcardkey	Generate a subkey on a card and add it to this key.
keytocard	Transfer the selected secret subkey (or the primary key if no subkey has been selected) to a smartcard. The secret key in the keyring will be replaced by a stub if the key could be stored successfully on the card and you use the save command later. Only certain key types may be transferred to the card. A sub menu allows you to select on what card to store the key. Note that it is not possible to get that key back from the card - if the card gets broken your secret key will be lost unless you have a backup somewhere.
bkuptocard <i>file</i>	Restore the given <i>file</i> to a card. This command may be used to restore a backup key (as generated during card initialization) to a new card. In almost all cases this will be the encryption key. You should use this command only with the corresponding public key and make sure that the file given as argument is indeed the backup to restore. You should then select 2 to restore as encryption key. You will first be asked to enter the passphrase of the backup key and then for the Admin PIN of the card.
delkey	Remove a subkey (secondary key). Note that it is not possible to retract a subkey, once it has been send to the public (i.e. to a keyserver). In that case you better use revkey . Also note that this only deletes the public part of a key.
revkey	Revoke a subkey.
expire	Change the key or subkey expiration time. If a subkey is selected, the expiration time of this subkey will be changed. With no selection, the key expiration of the primary key is changed.
trust	Change the owner trust value for the key. This updates the trust-db immediately and no save is required.

disable	
enable	Disable or enable an entire key. A disabled key can not normally be used for encryption.
addrevoker	Add a designated revoker to the key. This takes one optional argument: "sensitive". If a designated revoker is marked as sensitive, it will not be exported by default (see export-options).
passwd	Change the passphrase of the secret key.
toggle	This is dummy command which exists only for backward compatibility.
clean	Compact (by removing all signatures except the selfsig) any user ID that is no longer usable (e.g. revoked, or expired). Then, remove any signatures that are not usable by the trust calculations. Specifically, this removes any signature that does not validate, any signature that is superseded by a later signature, revoked signatures, and signatures issued by keys that are not present on the keyring.
minimize	Make the key as small as possible. This removes all signatures from each user ID except for the most recent self-signature.
change-usage	Change the usage flags (capabilities) of the primary key or of subkeys. These usage flags (e.g. Certify, Sign, Authenticate, Encrypt) are set during key creation. Sometimes it is useful to have the opportunity to change them (for example to add Authenticate) after they have been created. Please take care when doing this; the allowed usage flags depend on the key algorithm.
cross-certify	Add cross-certification signatures to signing subkeys that may not currently have them. Cross-certification signatures protect against a subtle attack against signing subkeys. See ' --require-cross-certification '. All new keys generated have this signature by default, so this command is only useful to bring older keys up to date.
save	Save all changes to the keyrings and quit.
quit	Quit the program without updating the keyrings.

The listing shows you the key with its secondary keys and all user IDs. The primary user ID is indicated by a dot, and selected keys or user IDs are indicated by an asterisk. The trust value is displayed with the primary key: "trust" is the assigned owner trust and "validity" is the calculated validity of the key. Validity values are also displayed for all user IDs. For possible values of trust, see [\[trust-values\]](#), page 133.

--sign-key *name*

Signs a public key with your secret key. This is a shortcut version of the subcommand "sign" from '**--edit**'.

--lsign-key *name*

Signs a public key with your secret key but marks it as non-exportable. This is a shortcut version of the subcommand "lsign" from '**--edit-key**'.

--quick-sign-key *fpr* [*names*]**--quick-lsign-key *fpr* [*names*]**

Directly sign a key from the passphrase without any further user interaction. The *fpr* must be the verified primary fingerprint of a key in the local keyring. If no *names* are given, all useful user ids are signed; with given [*names*] only useful user ids matching one of these names are signed. By default, or if a name is prefixed with a '*', a case insensitive substring match is used. If a name is prefixed with a '=' a case sensitive exact match is done.

The command '**--quick-lsign-key**' marks the signatures as non-exportable. If such a non-exportable signature already exists the '**--quick-sign-key**' turns it into a exportable signature.

This command uses reasonable defaults and thus does not provide the full flexibility of the "sign" subcommand from '**--edit-key**'. Its intended use is to help unattended key signing by utilizing a list of verified fingerprints.

--quick-add-uid *user-id* *new-user-id*

This command adds a new user id to an existing key. In contrast to the interactive sub-command **adduid** of '**--edit-key**' the *new-user-id* is added verbatim with only leading and trailing white space removed, it is expected to be UTF-8 encoded, and no checks on its form are applied.

--quick-revoke-uid *user-id* *user-id-to-revoke*

This command revokes a user ID on an existing key. It cannot be used to revoke the last user ID on key (some non-revoked user ID must remain), with revocation reason "User ID is no longer valid". If you want to specify a different revocation reason, or to supply supplementary revocation text, you should use the interactive sub-command **revuid** of '**--edit-key**'.

--quick-revoke-sig *fpr* *signing-fpr* [*names*]

This command revokes the key signatures made by *signing-fpr* from the key specified by the fingerprint *fpr*. With *names* given only the signatures on user ids of the key matching any of the given names are affected (see '**--quick-sign-key**'). If a revocation already exists a notice is printed instead of creating a new revocation; no error is returned in this case. Note that key signature revocations may be superseded by a newer key signature and in turn again revoked.

--quick-set-primary-uid *user-id* *primary-user-id*

This command sets or updates the primary user ID flag on an existing key. *user-id* specifies the key and *primary-user-id* the user ID which shall be flagged as the primary user ID. The primary user ID flag is removed from all other user ids and the timestamp of all affected self-signatures is set one second ahead.

--change-passphrase *user-id*
--passwd *user-id*

Change the passphrase of the secret key belonging to the certificate specified as *user-id*. This is a shortcut for the sub-command **passwd** of the edit key menu. When using together with the option ‘**--dry-run**’ this will not actually change the passphrase but check that the current passphrase is correct.

4.2 Option Summary

gpg2 features a bunch of options to control the exact behaviour and to change the default configuration.

Long options can be put in an options file (default “`~/gnupg/gpg.conf`”). Short option names will not work - for example, “armor” is a valid option for the options file, while “a” is not. Do not write the 2 dashes, but simply the name of the option and any required arguments. Lines with a hash (`#`) as the first non-white-space character are ignored. Commands may be put in this file too, but that is not generally useful as the command will execute automatically with every execution of **gpg**.

Please remember that option parsing stops as soon as a non-option is encountered, you can explicitly stop parsing by using the special option ‘**--**’.

4.2.1 How to change the configuration

These options are used to change the configuration and are usually found in the option file.

--default-key *name*

Use *name* as the default key to sign with. If this option is not used, the default key is the first key found in the secret keyring. Note that ‘**-u**’ or ‘**--local-user**’ overrides this option. This option may be given multiple times. In this case, the last key for which a secret key is available is used. If there is no secret key available for any of the specified values, GnuPG will not emit an error message but continue as if this option wasn’t given.

--default-recipient *name*

Use *name* as default recipient if option ‘**--recipient**’ is not used and don’t ask if this is a valid one. *name* must be non-empty.

--default-recipient-self

Use the default key as default recipient if option ‘**--recipient**’ is not used and don’t ask if this is a valid one. The default key is the first one from the secret keyring or the one set with ‘**--default-key**’.

--no-default-recipient

Reset ‘**--default-recipient**’ and ‘**--default-recipient-self**’.

-v, --verbose

Give more information during processing. If used twice, the input data is listed in detail.

--no-verbose

Reset verbose level to 0.

-q, --quiet

Try to be as quiet as possible.

--batch

--no-batch

Use batch mode. Never ask, do not allow interactive commands. ‘**--no-batch**’ disables this option. Note that even with a filename given on the command line, gpg might still need to read from STDIN (in particular if gpg figures that the input is a detached signature and no data file has been specified). Thus if you do not want to feed data via STDIN, you should connect STDIN to g‘/dev/null’.

It is highly recommended to use this option along with the options ‘**--status-fd**’ and ‘**--with-colons**’ for any unattended use of gpg.

--no-tty Make sure that the TTY (terminal) is never used for any output. This option is needed in some cases because GnuPG sometimes prints warnings to the TTY even if ‘**--batch**’ is used.

--yes Assume "yes" on most questions.

--no Assume "no" on most questions.

--list-options *parameters*

This is a space or comma delimited string that gives options used when listing keys and signatures (that is, ‘**--list-keys**’, ‘**--check-signatures**’, ‘**--list-public-keys**’, ‘**--list-secret-keys**’, and the ‘**--edit-key**’ functions). Options can be prepended with a ‘no-’ (after the two dashes) to give the opposite meaning. The options are:

show-photos

Causes ‘**--list-keys**’, ‘**--check-signatures**’, ‘**--list-public-keys**’, and ‘**--list-secret-keys**’ to display any photo IDs attached to the key. Defaults to no. See also ‘**--photo-viewer**’. Does not work with ‘**--with-colons**’: see ‘**--attribute-fd**’ for the appropriate way to get photo data for scripts and other frontends.

show-usage

Show usage information for keys and subkeys in the standard key listing. This is a list of letters indicating the allowed usage for a key (E=encryption, S=signing, C=certification, A=authentication). Defaults to yes.

show-policy-urls

Show policy URLs in the ‘**--check-signatures**’ listings. Defaults to no.

show-notations

show-std-notations

show-user-notations

Show all, IETF standard, or user-defined signature notations in the ‘**--check-signatures**’ listings. Defaults to no.

- show-keyserver-urls
Show any preferred keyserver URL in the ‘**--check-signatures**’ listings. Defaults to no.
- show-uid-validity
Display the calculated validity of user IDs during key listings. Defaults to yes.
- show-unusable-uids
Show revoked and expired user IDs in key listings. Defaults to no.
- show-unusable-subkeys
Show revoked and expired subkeys in key listings. Defaults to no.
- show-keyring
Display the keyring name at the head of key listings to show which keyring a given key resides on. Defaults to no.
- show-sig-expire
Show signature expiration dates (if any) during ‘**--check-signatures**’ listings. Defaults to no.
- show-sig-subpackets
Include signature subpackets in the key listing. This option can take an optional argument list of the subpackets to list. If no argument is passed, list all subpackets. Defaults to no. This option is only meaningful when using ‘**--with-colons**’ along with ‘**--check-signatures**’.
- show-only-fpr-mbox
For each user-id which has a valid mail address print only the fingerprint followed by the mail address.

--verify-options *parameters*

This is a space or comma delimited string that gives options used when verifying signatures. Options can be prepended with a ‘no-’ to give the opposite meaning. The options are:

- show-photos
Display any photo IDs present on the key that issued the signature. Defaults to no. See also ‘**--photo-viewer**’.
- show-policy-urls
Show policy URLs in the signature being verified. Defaults to yes.
- show-notations
- show-std-notations
- show-user-notations
Show all, IETF standard, or user-defined signature notations in the signature being verified. Defaults to IETF standard.
- show-keyserver-urls
Show any preferred keyserver URL in the signature being verified. Defaults to yes.

`show-uid-validity`
 Display the calculated validity of the user IDs on the key that issued the signature. Defaults to yes.

`show-unusable-uids`
 Show revoked and expired user IDs during signature verification. Defaults to no.

`show-primary-uid-only`
 Show only the primary user ID during signature verification. That is all the AKA lines as well as photo IDs are not shown with the signature verification status.

`pka-lookups`
 Enable PKA lookups to verify sender addresses. Note that PKA is based on DNS, and so enabling this option may disclose information on when and what signatures are verified or to whom data is encrypted. This is similar to the "web bug" described for the '`--auto-key-retrieve`' option.

`pka-trust-increase`
 Raise the trust in a signature to full if the signature passes PKA validation. This option is only meaningful if `pka-lookups` is set.

`--enable-large-rsa`

`--disable-large-rsa`

With `-generate-key` and `-batch`, enable the creation of RSA secret keys as large as 8192 bit. Note: 8192 bit is more than is generally recommended. These large keys don't significantly improve security, but they are more expensive to use, and their signatures and certifications are larger. This option is only available if the binary was build with large-secmem support.

`--enable-dsa2`

`--disable-dsa2`

Enable hash truncation for all DSA keys even for old DSA Keys up to 1024 bit. This is also the default with '`--openpgp`'. Note that older versions of GnuPG also required this flag to allow the generation of DSA larger than 1024 bit.

`--photo-viewer string`

This is the command line that should be run to view a photo ID. "%i" will be expanded to a filename containing the photo. "%I" does the same, except the file will not be deleted once the viewer exits. Other flags are "%k" for the key ID, "%K" for the long key ID, "%f" for the key fingerprint, "%t" for the extension of the image type (e.g. "jpg"), "%T" for the MIME type of the image (e.g. "image/jpeg"), "%v" for the single-character calculated validity of the image being viewed (e.g. "f"), "%V" for the calculated validity as a string (e.g. "full"), "%U" for a base32 encoded hash of the user ID, and "%%" for an actual percent sign. If neither %i or %I are present, then the photo will be supplied to the viewer on standard input.

On Unix the default viewer is `xloadimage -fork -quiet -title 'KeyID 0x%k' STDIN` with a fallback to `display -title 'KeyID 0x%k' %i` and finally to `xdg-`

open %i. On Windows !ShellExecute 400 %i is used; here the command is a meta command to use that API call followed by a wait time in milliseconds which is used to give the viewer time to read the temporary image file before gpg deletes it again. Note that if your image viewer program is not secure, then executing it from gpg does not make it secure.

--exec-path *string*

Sets a list of directories to search for photo viewers. If not provided, photo viewers use the PATH environment variable.

--keyring *file*

Add *file* to the current list of keyrings. If *file* begins with a tilde and a slash, these are replaced by the \$HOME directory. If the filename does not contain a slash, it is assumed to be in the GnuPG home directory ("~/gnupg" if '--homedir' or \$GNUPGHOME is not used).

Note that this adds a keyring to the current list. If the intent is to use the specified keyring alone, use '--keyring' along with '--no-default-keyring'.

If the option '--no-keyring' has been used, no keyrings will be used at all.

--secret-keyring *file*

This is an obsolete option and is ignored. All secret keys are stored in the 'private-keys-v1.d' directory below the GnuPG home directory.

--primary-keyring *file*

Designate *file* as the primary public keyring. This means that newly imported keys (via '--import' or keyserver '--recv-from') will go to this keyring.

--trustdb-name *file*

Use *file* instead of the default trustdb. If *file* begins with a tilde and a slash, these are replaced by the \$HOME directory. If the filename does not contain a slash, it is assumed to be in the GnuPG home directory ('~/gnupg' if '--homedir' or \$GNUPGHOME is not used).

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to '~/gnupg'. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable GNUPGHOME or (on Windows systems) by means of the Registry entry HKCU\Software\GNU\GnuPG:HomeDir.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named 'gpgconf.ct1' in the same directory as the tool 'gpgconf.exe'. The root of the installation is then that directory; or, if 'gpgconf.exe' has been installed directly below a directory named 'bin', its parent directory. You also need to make sure that the following directories exist and are writable: 'ROOT/home' for the GnuPG home and 'ROOT/var/cache/gnupg' for internal cache files.

--display-charset *name*

Set the name of the native character set. This is used to convert some informational strings like user IDs to the proper UTF-8 encoding. Note that this has nothing to do with the character set of data to be encrypted or signed; GnuPG does not recode user-supplied data. If this option is not used, the default character set is determined from the current locale. A verbosity level of 3 shows the chosen set. Valid values for *name* are:

iso-8859-1 This is the Latin 1 set.

iso-8859-2 The Latin 2 set.

iso-8859-15
This is currently an alias for the Latin 1 set.

koi8-r The usual Russian set (RFC-1489).

utf-8 Bypass all translations and assume that the OS uses native UTF-8 encoding.

--utf8-strings**--no-utf8-strings**

Assume that command line arguments are given as UTF-8 strings. The default ('--no-utf8-strings') is to assume that arguments are encoded in the character set as specified by '--display-charset'. These options affect all following arguments. Both options may be used multiple times.

--options *file*

Read options from *file* and do not try to read them from the default options file in the homedir (see '--homedir'). This option is ignored if used in an options file.

--no-options

Shortcut for '--options /dev/null'. This option is detected before an attempt to open an option file. Using this option will also prevent the creation of a '~/.gnupg' homedir.

-z *n***--compress-level *n*****--bzip2-compress-level *n***

Set compression level to *n* for the ZIP and ZLIB compression algorithms. The default is to use the default compression level of zlib (normally 6). '--bzip2-compress-level' sets the compression level for the BZIP2 compression algorithm (defaulting to 6 as well). This is a different option from '--compress-level' since BZIP2 uses a significant amount of memory for each additional compression level. '-z' sets both. A value of 0 for *n* disables compression.

--bzip2-decompress-lowmem

Use a different decompression method for BZIP2 compressed files. This alternate method uses a bit more than half the memory, but also runs at half the speed. This is useful under extreme low memory circumstances when the file was originally compressed at a high '--bzip2-compress-level'.

`--mangle-dos-filenames`

`--no-mangle-dos-filenames`

Older version of Windows cannot handle filenames with more than one dot. ‘`--mangle-dos-filenames`’ causes GnuPG to replace (rather than add to) the extension of an output filename to avoid this problem. This option is off by default and has no effect on non-Windows platforms.

`--ask-cert-level`

`--no-ask-cert-level`

When making a key signature, prompt for a certification level. If this option is not specified, the certification level used is set via ‘`--default-cert-level`’. See ‘`--default-cert-level`’ for information on the specific levels and how they are used. ‘`--no-ask-cert-level`’ disables this option. This option defaults to no.

`--default-cert-level n`

The default to use for the check level when signing a key.

0 means you make no particular claim as to how carefully you verified the key.

1 means you believe the key is owned by the person who claims to own it but you could not, or did not verify the key at all. This is useful for a "persona" verification, where you sign the key of a pseudonymous user.

2 means you did casual verification of the key. For example, this could mean that you verified the key fingerprint and checked the user ID on the key against a photo ID.

3 means you did extensive verification of the key. For example, this could mean that you verified the key fingerprint with the owner of the key in person, and that you checked, by means of a hard to forge document with a photo ID (such as a passport) that the name of the key owner matches the name in the user ID on the key, and finally that you verified (by exchange of email) that the email address on the key belongs to the key owner.

Note that the examples given above for levels 2 and 3 are just that: examples. In the end, it is up to you to decide just what "casual" and "extensive" mean to you.

This option defaults to 0 (no particular claim).

`--min-cert-level`

When building the trust database, treat any signatures with a certification level below this as invalid. Defaults to 2, which disregards level 1 signatures. Note that level 0 "no particular claim" signatures are always accepted.

`--trusted-key long key ID or fingerprint`

Assume that the specified key (which must be given as a full 8 byte key ID or 20 byte fingerprint) is as trustworthy as one of your own secret keys. This option is useful if you don’t want to keep your secret keys (or one of them) online but still want to be able to check the validity of a given recipient’s or signator’s key.

`--trust-model {pgp|classic|tofu|tofu+pgp|direct|always|auto}`

Set what trust model GnuPG should follow. The models are:

pgp	This is the Web of Trust combined with trust signatures as used in PGP 5.x and later. This is the default trust model when creating a new trust database.
classic	This is the standard Web of Trust as introduced by PGP 2.
tofu	TOFU stands for Trust On First Use. In this trust model, the first time a key is seen, it is memorized. If later another key with a user id with the same email address is seen, both keys are marked as suspect. In that case, the next time either is used, a warning is displayed describing the conflict, why it might have occurred (either the user generated a new key and failed to cross sign the old and new keys, the key is forgery, or a man-in-the-middle attack is being attempted), and the user is prompted to manually confirm the validity of the key in question.

Because a potential attacker is able to control the email address and thereby circumvent the conflict detection algorithm by using an email address that is similar in appearance to a trusted email address, whenever a message is verified, statistics about the number of messages signed with the key are shown. In this way, a user can easily identify attacks using fake keys for regular correspondents.

When compared with the Web of Trust, TOFU offers significantly weaker security guarantees. In particular, TOFU only helps ensure consistency (that is, that the binding between a key and email address doesn't change). A major advantage of TOFU is that it requires little maintenance to use correctly. To use the web of trust properly, you need to actively sign keys and mark users as trusted introducers. This is a time-consuming process and anecdotal evidence suggests that even security-conscious users rarely take the time to do this thoroughly and instead rely on an ad-hoc TOFU process.

In the TOFU model, policies are associated with bindings between keys and email addresses (which are extracted from user ids and normalized). There are five policies, which can be set manually using the `'--tofu-policy'` option. The default policy can be set using the `'--tofu-default-policy'` option.

The TOFU policies are: `auto`, `good`, `unknown`, `bad` and `ask`. The `auto` policy is used by default (unless overridden by `'--tofu-default-policy'`) and marks a binding as marginally trusted. The `good`, `unknown` and `bad` policies mark a binding as fully trusted, as having unknown trust or as having trust never, respectively. The `unknown` policy is useful for just using TOFU to detect conflicts, but to never assign positive trust to a binding. The final policy, `ask` prompts the user to indicate the binding's trust. If batch mode is enabled (or input is inappropriate in the context), then the user is not prompted and the `undefined` trust level is returned.

- tofu+pgp** This trust model combines TOFU with the Web of Trust. This is done by computing the trust level for each model and then taking the maximum trust level where the trust levels are ordered as follows: **unknown** < **undefined** < **marginal** < **fully** < **ultimate** < **expired** < **never**.
- By setting '**--tofu-default-policy=unknown**', this model can be used to implement the web of trust with TOFU's conflict detection algorithm, but without its assignment of positive trust values, which some security-conscious users don't like.
- direct** Key validity is set directly by the user and not calculated via the Web of Trust. This model is solely based on the key and does not distinguish user IDs. Note that when changing to another trust model the trust values assigned to a key are transformed into ownertrust values, which also indicate how you trust the owner of the key to sign other keys.
- always** Skip key validation and assume that used keys are always fully valid. You generally won't use this unless you are using some external validation scheme. This option also suppresses the "[uncertain]" tag printed with signature checks when there is no evidence that the user ID is bound to the key. Note that this trust model still does not allow the use of expired, revoked, or disabled keys.
- auto** Select the trust model depending on whatever the internal trust database says. This is the default model if such a database already exists. Note that a tofu trust model is not considered here and must be enabled explicitly.

--auto-key-locate *mechanisms*

--no-auto-key-locate

GnuPG can automatically locate and retrieve keys as needed using this option. This happens when encrypting to an email address (in the "user@example.com" form), and there are no "user@example.com" keys on the local keyring. This option takes any number of the mechanisms listed below, in the order they are to be tried. Instead of listing the mechanisms as comma delimited arguments, the option may also be given several times to add more mechanism. The option '**--no-auto-key-locate**' or the mechanism "clear" resets the list. The default is "local,wkd".

- cert** Locate a key using DNS CERT, as specified in RFC-4398.
- pka** Locate a key using DNS PKA.
- dane** Locate a key using DANE, as specified in draft-ietf-dane-openpgpkey-05.txt.
- wkd** Locate a key using the Web Key Directory protocol.
- ldap** Using DNS Service Discovery, check the domain in question for any LDAP key servers to use. If this fails, attempt to

- locate the key using the PGP Universal method of checking 'ldap://keys.(thedomain)'.
- ntds Locate the key using the Active Directory (Windows only).
- keyserver Locate a key using a keyserver.
- keyserver-URL
In addition, a keyserver URL as used in the `dirmngr` configuration may be used here to query that particular keyserver.
- local Locate the key using the local keyrings. This mechanism allows the user to select the order a local key lookup is done. Thus using '`--auto-key-locate local`' is identical to '`--no-auto-key-locate`'.
- nodefault This flag disables the standard local key lookup, done before any of the mechanisms defined by the '`--auto-key-locate`' are tried. The position of this mechanism in the list does not matter. It is not required if `local` is also used.
- clear Clear all defined mechanisms. This is useful to override mechanisms given in a config file. Note that a `nodefault` in *mechanisms* will also be cleared unless it is given after the `clear`.
- `--auto-key-import`
`--no-auto-key-import`
This is an offline mechanism to get a missing key for signature verification and for later encryption to this key. If this option is enabled and a signature includes an embedded key, that key is used to verify the signature and on verification success that key is imported. The default is '`--no-auto-key-import`'.
- On the sender (signing) site the option '`--include-key-block`' needs to be used to put the public part of the signing key as Key Block subpacket into the signature.
- `--auto-key-retrieve`
`--no-auto-key-retrieve`
These options enable or disable the automatic retrieving of keys from a keyserver when verifying signatures made by keys that are not on the local keyring. The default is '`--no-auto-key-retrieve`'.
- The order of methods tried to lookup the key is:
1. If the option '`--auto-key-import`' is set and the signatures includes an embedded key, that key is used to verify the signature and on verification success that key is imported.
 2. If a preferred keyserver is specified in the signature and the option '`--honor-keyserver-url`' is active (which is not the default), that keyserver is tried. Note that the creator of the signature uses the option '`--sig-keyserver-url`' to specify the preferred keyserver for data signatures.
 3. If the signature has the Signer's UID set (e.g. using '`--sender`' while creating the signature) a Web Key Directory (WKD) lookup is done. This is the default

configuration but can be disabled by removing WKD from the auto-key-locate list or by using the option ‘`--disable-signer-uid`’.

4. If the option ‘`honor-pka-record`’ is active, the legacy PKA method is used.

5. If any keyserver is configured and the Issuer Fingerprint is part of the signature (since GnuPG 2.1.16), the configured keyservers are tried.

Note that this option makes a "web bug" like behavior possible. Keyserver or Web Key Directory operators can see which keys you request, so by sending you a message signed by a brand new key (which you naturally will not have on your local keyring), the operator can tell both your IP address and the time when you verified the signature.

`--keyid-format {none|short|0xshort|long|0xlong}`

Select how to display key IDs. "none" does not show the key ID at all but shows the fingerprint in a separate line. "short" is the traditional 8-character key ID. "long" is the more accurate (but less convenient) 16-character key ID. Add an "0x" to either to include an "0x" at the beginning of the key ID, as in 0x99242560. Note that this option is ignored if the option ‘`--with-colons`’ is used.

`--keyserver name`

This option is deprecated - please use the ‘`--keyserver`’ in ‘`dirmngr.conf`’ instead.

Use *name* as your keyserver. This is the server that ‘`--receive-keys`’, ‘`--send-keys`’, and ‘`--search-keys`’ will communicate with to receive keys from, send keys to, and search for keys on. The format of the *name* is a URI: ‘`scheme://keyservername[:port]`’ The scheme is the type of keyserver: "hkp" for the HTTP (or compatible) keyservers, "ldap" for the LDAP keyservers, or "mailto" for the Graff email keyserver. Note that your particular installation of GnuPG may have other keyserver types available as well. Keyserver schemes are case-insensitive. After the keyserver name, optional keyserver configuration options may be provided. These are the same as the global ‘`--keyserver-options`’ from below, but apply only to this particular keyserver.

Most keyservers synchronize with each other, so there is generally no need to send keys to more than one server. The keyserver `hkp://keys.gnupg.net` uses round robin DNS to give a different keyserver each time you use it.

`--keyserver-options {name=value}`

This is a space or comma delimited string that gives options for the keyserver. Options can be prefixed with a ‘no-’ to give the opposite meaning. Valid import-options or export-options may be used here as well to apply to importing (‘`--recv-key`’) or exporting (‘`--send-key`’) a key from a keyserver. While not all options are available for all keyserver types, some common options are:

include-revoked

When searching for a key with ‘`--search-keys`’, include keys that are marked on the keyserver as revoked. Note that not all key-servers differentiate between revoked and unrevoked keys, and for

such keyserver this option is meaningless. Note also that most keyserver do not have cryptographic verification of key revocations, and so turning this option off may result in skipping keys that are incorrectly marked as revoked.

include-disabled

When searching for a key with ‘**--search-keys**’, include keys that are marked on the keyserver as disabled. Note that this option is not used with HKP keyserver.

auto-key-retrieve

This is an obsolete alias for the option ‘**auto-key-retrieve**’. Please do not use it; it will be removed in future versions..

honor-keyserver-url

When using ‘**--refresh-keys**’, if the key in question has a preferred keyserver URL, then use that preferred keyserver to refresh the key from. In addition, if **auto-key-retrieve** is set, and the signature being verified has a preferred keyserver URL, then use that preferred keyserver to fetch the key from. Note that this option introduces a "web bug": The creator of the key can see when the keys is refreshed. Thus this option is not enabled by default.

honor-pka-record

If ‘**--auto-key-retrieve**’ is used, and the signature being verified has a PKA record, then use the PKA information to fetch the key. Defaults to "yes".

include-subkeys

When receiving a key, include subkeys as potential targets. Note that this option is not used with HKP keyserver, as they do not support retrieving keys by subkey id.

timeout

http-proxy=value

verbose

debug

check-cert

ca-cert-file These options have no more function since GnuPG 2.1. Use the **dirmngr** configuration options instead.

The default list of options is: "self-sigs-only, import-clean, repair-keys, repair-pks-subkey-bug, export-attributes, honor-pka-record".

--completes-needed n

Number of completely trusted users to introduce a new key signer (defaults to 1).

--marginals-needed n

Number of marginally trusted users to introduce a new key signer (defaults to 3)

--tofu-default-policy {auto|good|unknown|bad|ask}
 The default TOFU policy (defaults to `auto`). For more information about the meaning of this option, see [\[trust-model-tofu\]](#), page 57.

--max-cert-depth *n*
 Maximum depth of a certification chain (default is 5).

--no-sig-cache
 Do not cache the verification status of key signatures. Caching gives a much better performance in key listings. However, if you suspect that your public keyring is not safe against write modifications, you can use this option to disable the caching. It probably does not make sense to disable it because all kind of damage can be done if someone else has write access to your public keyring.

--auto-check-trustdb
--no-auto-check-trustdb
 If GnuPG feels that its information about the Web of Trust has to be updated, it automatically runs the `--check-trustdb` command internally. This may be a time consuming process. `--no-auto-check-trustdb` disables this option.

--use-agent
--no-use-agent
 This is dummy option. `gpg2` always requires the agent.

--gpg-agent-info
 This is dummy option. It has no effect when used with `gpg2`.

--agent-program *file*
 Specify an agent program to be used for secret key operations. The default value is determined by running `gpgconf` with the option `--list-dirs`. Note that the pipe symbol (`|`) is used for a regression test suite hack and may thus not be used in the file name.

--dirmngr-program *file*
 Specify a `dirmngr` program to be used for keyserver access. The default value is `/usr/bin/dirmngr`.

--disable-dirmngr
 Entirely disable the use of the `Dirmngr`.

--no-autostart
 Do not start the `gpg-agent` or the `dirmngr` if it has not yet been started and its service is required. This option is mostly useful on machines where the connection to `gpg-agent` has been redirected to another machines. If `dirmngr` is required on the remote machine, it may be started manually using `gpgconf --launch dirmngr`.

--lock-once
 Lock the databases the first time a lock is requested and do not release the lock until the process terminates.

--lock-multiple
 Release the locks every time a lock is no longer needed. Use this to override a previous `--lock-once` from a config file.

--lock-never

Disable locking entirely. This option should be used only in very special environments, where it can be assured that only one process is accessing those files. A bootable floppy with a stand-alone encryption system will probably use this. Improper usage of this option may lead to data and key corruption.

--exit-on-status-write-error

This option will cause write errors on the status FD to immediately terminate the process. That should in fact be the default but it never worked this way and thus we need an option to enable this, so that the change won't break applications which close their end of a status fd connected pipe too early. Using this option along with '**--enable-progress-filter**' may be used to cleanly cancel long running gpg operations.

--limit-card-insert-tries n

With *n* greater than 0 the number of prompts asking to insert a smartcard gets limited to *N*-1. Thus with a value of 1 gpg won't at all ask to insert a card if none has been inserted at startup. This option is useful in the configuration file in case an application does not know about the smartcard support and waits ad infinitum for an inserted card.

--no-random-seed-file

GnuPG uses a file to store its internal random pool over invocations. This makes random generation faster; however sometimes write operations are not desired. This option can be used to achieve that with the cost of slower random generation.

--no-greeting

Suppress the initial copyright message.

--no-secmem-warning

Suppress the warning about "using insecure memory".

--no-permission-warning

Suppress the warning about unsafe file and home directory ('**--homedir**') permissions. Note that the permission checks that GnuPG performs are not intended to be authoritative, but rather they simply warn about certain common permission problems. Do not assume that the lack of a warning means that your system is secure.

Note that the warning for unsafe '**--homedir**' permissions cannot be suppressed in the gpg.conf file, as this would allow an attacker to place an unsafe gpg.conf file in place, and use this file to suppress warnings about itself. The '**--homedir**' permissions warning may only be suppressed on the command line.

--require-secmem**--no-require-secmem**

Refuse to run if GnuPG cannot get secure memory. Defaults to no (i.e. run, but give a warning).

`--require-cross-certification`

`--no-require-cross-certification`

When verifying a signature made from a subkey, ensure that the cross certification "back signature" on the subkey is present and valid. This protects against a subtle attack against subkeys that can sign. Defaults to `'--require-cross-certification'` for `gpg2`.

`--expert`

`--no-expert`

Allow the user to do certain nonsensical or "silly" things like signing an expired or revoked key, or certain potentially incompatible things like generating unusual key types. This also disables certain warning messages about potentially incompatible actions. As the name implies, this option is for experts only. If you don't fully understand the implications of what it allows you to do, leave this off. `'--no-expert'` disables this option.

4.2.2 Key related options

`--recipient name`

`-r` Encrypt for user id *name*. If this option or `'--hidden-recipient'` is not specified, GnuPG asks for the user-id unless `'--default-recipient'` is given.

`--hidden-recipient name`

`-R` Encrypt for user ID *name*, but hide the key ID of this user's key. This option helps to hide the receiver of the message and is a limited countermeasure against traffic analysis. If this option or `'--recipient'` is not specified, GnuPG asks for the user ID unless `'--default-recipient'` is given.

`--recipient-file file`

`-f` This option is similar to `'--recipient'` except that it encrypts to a key stored in the given file. *file* must be the name of a file containing exactly one key. `gpg2` assumes that the key in this file is fully valid.

`--hidden-recipient-file file`

`-F` This option is similar to `'--hidden-recipient'` except that it encrypts to a key stored in the given file. *file* must be the name of a file containing exactly one key. `gpg2` assumes that the key in this file is fully valid.

`--encrypt-to name`

Same as `'--recipient'` but this one is intended for use in the options file and may be used with your own user-id as an "encrypt-to-self". These keys are only used when there are other recipients given either by use of `'--recipient'` or by the asked user id. No trust checking is performed for these user ids and even disabled keys can be used.

`--hidden-encrypt-to name`

Same as `'--hidden-recipient'` but this one is intended for use in the options file and may be used with your own user-id as a hidden "encrypt-to-self". These keys are only used when there are other recipients given either by use of `'--recipient'` or by the asked user id. No trust checking is performed for these user ids and even disabled keys can be used.

- no-encrypt-to**
Disable the use of all '**--encrypt-to**' and '**--hidden-encrypt-to**' keys.
- group {name=value}**
Sets up a named group, which is similar to aliases in email programs. Any time the group name is a recipient ('**-r**' or '**--recipient**'), it will be expanded to the values specified. Multiple groups with the same name are automatically merged into a single group.
- The values are key IDs or fingerprints, but any key description is accepted. Note that a value with spaces in it will be treated as two different values. Note also there is only one level of expansion — you cannot make an group that points to another group. When used from the command line, it may be necessary to quote the argument to this option to prevent the shell from treating it as multiple arguments.
- ungroup name**
Remove a given entry from the '**--group**' list.
- no-groups**
Remove all entries from the '**--group**' list.
- local-user name**
-u Use *name* as the key to sign with. Note that this option overrides '**--default-key**'.
- sender mbox**
This option has two purposes. *mbox* must either be a complete user id with a proper mail address or just a mail address. When creating a signature this option tells gpg the user id of a key used to make a signature if the key was not directly specified by a user id. When verifying a signature the *mbox* is used to restrict the information printed by the TOFU code to matching user ids.
- try-secret-key name**
For hidden recipients GPG needs to know the keys to use for trial decryption. The key set with '**--default-key**' is always tried first, but this is often not sufficient. This option allows setting more keys to be used for trial decryption. Although any valid user-id specification may be used for *name* it makes sense to use at least the long keyid to avoid ambiguities. Note that gpg-agent might pop up a pinentry for a lot keys to do the trial decryption. If you want to stop all further trial decryption you may use close-window button instead of the cancel button.
- try-all-secrets**
Don't look at the key ID as stored in the message but try all secret keys in turn to find the right decryption key. This option forces the behaviour as used by anonymous recipients (created by using '**--throw-keyids**' or '**--hidden-recipient**') and might come handy in case where an encrypted message contains a bogus key ID.

`--skip-hidden-recipients`

`--no-skip-hidden-recipients`

During decryption skip all anonymous recipients. This option helps in the case that people use the hidden recipients feature to hide their own encrypt-to key from others. If one has many secret keys this may lead to a major annoyance because all keys are tried in turn to decrypt something which was not really intended for it. The drawback of this option is that it is currently not possible to decrypt a message which includes real anonymous recipients.

4.2.3 Input and Output

`--armor`

`-a` Create ASCII armored output. The default is to create the binary OpenPGP format.

`--no-armor`

Assume the input data is not in ASCII armored format.

`--output file`

`-o file` Write output to *file*. To write to stdout use `-` as the filename.

`--max-output n`

This option sets a limit on the number of bytes that will be generated when processing a file. Since OpenPGP supports various levels of compression, it is possible that the plaintext of a given message may be significantly larger than the original OpenPGP message. While GnuPG works properly with such messages, there is often a desire to set a maximum file size that will be generated before processing is forced to stop by the OS limits. Defaults to 0, which means "no limit".

`--input-size-hint n`

This option can be used to tell GPG the size of the input data in bytes. *n* must be a positive base-10 number. This option is only useful if the input is not taken from a file. GPG may use this hint to optimize its buffer allocation strategy. It is also used by the `'--status-fd'` line "PROGRESS" to provide a value for "total" if that is not available by other means.

`--key-origin string[,url]`

gpg can track the origin of a key. Certain origins are implicitly known (e.g. keyserver, web key directory) and set. For a standard import the origin of the keys imported can be set with this option. To list the possible values use "help" for *string*. Some origins can store an optional *url* argument. That URL can be appended to *string* after a comma.

`--import-options parameters`

This is a space or comma delimited string that gives options for importing keys. Options can be prepended with a 'no-' to give the opposite meaning. The options are:

import-local-sigs

Allow importing key signatures marked as "local". This is not generally useful unless a shared keyring scheme is being used. Defaults to no.

keep-ownertrust

Normally possible still existing ownertrust values of a key are cleared if a key is imported. This is in general desirable so that a formerly deleted key does not automatically gain an ownertrust values merely due to import. On the other hand it is sometimes necessary to re-import a trusted set of keys again but keeping already assigned ownertrust values. This can be achieved by using this option.

repair-pks-subkey-bug

During import, attempt to repair the damage caused by the PKS keyserver bug (pre version 0.9.6) that mangles keys with multiple subkeys. Note that this cannot completely repair the damaged key as some crucial data is removed by the keyserver, but it does at least give you back one subkey. Defaults to no for regular '**--import**' and to yes for keyserver '**--receive-keys**'.

import-show

show-only Show a listing of the key as imported right before it is stored. This can be combined with the option '**--dry-run**' to only look at keys; the option '**show-only**' is a shortcut for this combination. The command '**--show-keys**' is another shortcut for this. Note that suffixes like '#' for "sec" and "sbb" lines may or may not be printed.

import-export

Run the entire import code but instead of storing the key to the local keyring write it to the output. The export options '**export-pka**' and '**export-dane**' affect the output. This option can be used to remove all invalid parts from a key without the need to store it.

merge-only

During import, allow key updates to existing keys, but do not allow any new keys to be imported. Defaults to no.

import-clean

After import, compact (remove all signatures except the self-signature) any user IDs from the new key that are not usable. Then, remove any signatures from the new key that are not usable. This includes signatures that were issued by keys that are not present on the keyring. This option is the same as running the '**--edit-key**' command "clean" after import. Defaults to no.

self-sigs-only

Accept only self-signatures while importing a key. All other key signatures are skipped at an early import stage. This option can

be used with `keyserver-options` to mitigate attempts to flood a key with bogus signatures from a keyserver. The drawback is that all other valid key signatures, as required by the Web of Trust are also not imported. Note that when using this option along with `import-clean` it suppresses the final clean step after merging the imported key into the existing key.

`repair-keys`

After import, fix various problems with the keys. For example, this reorders signatures, and strips duplicate signatures. Defaults to yes.

`import-minimal`

Import the smallest key possible. This removes all signatures except the most recent self-signature on each user ID. This option is the same as running the '`--edit-key`' command "minimize" after import. Defaults to no.

`restore`

`import-restore`

Import in key restore mode. This imports all data which is usually skipped during import; including all GnuPG specific data. All other contradicting options are overridden.

`--import-filter {name=expr}`

`--export-filter {name=expr}`

These options define an import/export filter which are applied to the imported/exported keyblock right before it will be stored/written. *name* defines the type of filter to use, *expr* the expression to evaluate. The option can be used several times which then appends more expression to the same *name*.

The available filter types are:

`keep-uid` This filter will keep a user id packet and its dependent packets in the keyblock if the expression evaluates to true.

`drop-subkey`

This filter drops the selected subkeys. Currently only implemented for `--export-filter`.

`drop-sig`

This filter drops the selected key signatures on user ids. Self-signatures are not considered. Currently only implemented for `--import-filter`.

For the syntax of the expression see the chapter "FILTER EXPRESSIONS". The property names for the expressions depend on the actual filter type and are indicated in the following table.

The available properties are:

`uid` A string with the user id. (`keep-uid`)

`mbox` The `addr-spec` part of a user id with mailbox or the empty string. (`keep-uid`)

key_algo	A number with the public key algorithm of a key or subkey packet. (drop-subkey)
key_created	
key_created_d	The first is the timestamp a public key or subkey packet was created. The second is the same but given as an ISO string, e.g. "2016-08-17". (drop-subkey)
fpr	The hexified fingerprint of the current subkey or primary key. (drop-subkey)
primary	Boolean indicating whether the user id is the primary one. (keep-uid)
expired	Boolean indicating whether a user id (keep-uid), a key (drop-subkey), or a signature (drop-sig) expired.
revoked	Boolean indicating whether a user id (keep-uid) or a key (drop-subkey) has been revoked.
disabled	Boolean indicating whether a primary key is disabled. (not used)
secret	Boolean indicating whether a key or subkey is a secret one. (drop-subkey)
usage	A string indicating the usage flags for the subkey, from the sequence "ecsa?". For example, a subkey capable of just signing and authentication would be an exact match for "sa". (drop-subkey)
sig_created	
sig_created_d	The first is the timestamp a signature packet was created. The second is the same but given as an ISO date string, e.g. "2016-08-17". (drop-sig)
sig_algo	A number with the public key algorithm of a signature packet. (drop-sig)
sig_digest_algo	
	A number with the digest algorithm of a signature packet. (drop-sig)

--export-options *parameters*

This is a space or comma delimited string that gives options for exporting keys. Options can be prepended with a 'no-' to give the opposite meaning. The options are:

export-local-sigs

Allow exporting key signatures marked as "local". This is not generally useful unless a shared keyring scheme is being used. Defaults to no.

export-attributes

Include attribute user IDs (photo IDs) while exporting. Not including attribute user IDs is useful to export keys that are going to be

used by an OpenPGP program that does not accept attribute user IDs. Defaults to yes.

`export-sensitive-revkeys`

Include designated revoker information that was marked as "sensitive". Defaults to no.

`backup`

`export-backup`

Export for use as a backup. The exported data includes all data which is needed to restore the key or keys later with GnuPG. The format is basically the OpenPGP format but enhanced with GnuPG specific data. All other contradicting options are overridden.

`export-clean`

Compact (remove all signatures from) user IDs on the key being exported if the user IDs are not usable. Also, do not export any signatures that are not usable. This includes signatures that were issued by keys that are not present on the keyring. This option is the same as running the '`--edit-key`' command "clean" before export except that the local copy of the key is not modified. Defaults to no.

`export-minimal`

Export the smallest key possible. This removes all signatures except the most recent self-signature on each user ID. This option is the same as running the '`--edit-key`' command "minimize" before export except that the local copy of the key is not modified. Defaults to no.

`export-pka`

Instead of outputting the key material output PKA records suitable to put into DNS zone files. An ORIGIN line is printed before each record to allow diverting the records to the corresponding zone file.

`export-dane`

Instead of outputting the key material output OpenPGP DANE records suitable to put into DNS zone files. An ORIGIN line is printed before each record to allow diverting the records to the corresponding zone file.

`--with-colons`

Print key listings delimited by colons. Note that the output will be encoded in UTF-8 regardless of any '`--display-charset`' setting. This format is useful when GnuPG is called from scripts and other programs as it is easily machine parsed. The details of this format are documented in the file '`doc/DETAILS`', which is included in the GnuPG source distribution.

`--fixed-list-mode`

Do not merge primary user ID and primary key in '`--with-colon`' listing mode and print all timestamps as seconds since 1970-01-01. Since GnuPG 2.0.10, this

mode is always used and thus this option is obsolete; it does not harm to use it though.

--legacy-list-mode

Revert to the pre-2.1 public key list mode. This only affects the human readable output and not the machine interface (i.e. **--with-colons**). Note that the legacy format does not convey suitable information for elliptic curves.

--with-fingerprint

Same as the command '**--fingerprint**' but changes only the format of the output and may be used together with another command.

--with-subkey-fingerprint

If a fingerprint is printed for the primary key, this option forces printing of the fingerprint for all subkeys. This could also be achieved by using the '**--with-fingerprint**' twice but by using this option along with **keyid-format** "none" a compact fingerprint is printed.

--with-icao-spelling

Print the ICAO spelling of the fingerprint in addition to the hex digits.

--with-keygrip

Include the keygrip in the key listings. In **--with-colons** mode this is implicitly enable for secret keys.

--with-key-origin

Include the locally held information on the origin and last update of a key in a key listing. In **--with-colons** mode this is always printed. This data is currently experimental and shall not be considered part of the stable API.

--with-wkd-hash

Print a Web Key Directory identifier along with each user ID in key listings. This is an experimental feature and semantics may change.

--with-secret

Include info about the presence of a secret key in public key listings done with **--with-colons**.

4.2.4 OpenPGP protocol specific options

-t, --textmode

--no-textmode

Treat input files as text and store them in the OpenPGP canonical text form with standard "CRLF" line endings. This also sets the necessary flags to inform the recipient that the encrypted or signed data is text and may need its line endings converted back to whatever the local system uses. This option is useful when communicating between two platforms that have different line ending conventions (UNIX-like to Mac, Mac to Windows, etc). '**--no-textmode**' disables this option, and is the default.

```
--force-v3-sigs
--no-force-v3-sigs
--force-v4-certs
--no-force-v4-certs
```

These options are obsolete and have no effect since GnuPG 2.1.

```
--force-mdc
--disable-mdc
```

These options are obsolete and have no effect since GnuPG 2.2.8. The MDC is always used. But note: If the creation of a legacy non-MDC message is exceptionally required, the option ‘`--rfc2440`’ allows for this.

```
--disable-signer-uid
```

By default the user ID of the signing key is embedded in the data signature. As of now this is only done if the signing key has been specified with ‘`local-user`’ using a mail address, or with ‘`sender`’. This information can be helpful for verifier to locate the key; see option ‘`--auto-key-retrieve`’.

```
--include-key-block
```

This option is used to embed the actual signing key into a data signature. The embedded key is stripped down to a single user id and includes only the signing subkey used to create the signature as well as as valid encryption subkeys. All other info is removed from the key to keep it and thus the signature small. This option is the OpenPGP counterpart to the `gpgsm` option ‘`--include-certs`’.

```
--personal-cipher-preferences string
```

Set the list of personal cipher preferences to *string*. Use `gpg2--version` to get a list of available algorithms, and use `none` to set no preference at all. This allows the user to safely override the algorithm chosen by the recipient key preferences, as GPG will only select an algorithm that is usable by all recipients. The most highly ranked cipher in this list is also used for the ‘`--symmetric`’ encryption command.

```
--personal-digest-preferences string
```

Set the list of personal digest preferences to *string*. Use `gpg2--version` to get a list of available algorithms, and use `none` to set no preference at all. This allows the user to safely override the algorithm chosen by the recipient key preferences, as GPG will only select an algorithm that is usable by all recipients. The most highly ranked digest algorithm in this list is also used when signing without encryption (e.g. ‘`--clear-sign`’ or ‘`--sign`’).

```
--personal-compress-preferences string
```

Set the list of personal compression preferences to *string*. Use `gpg2--version` to get a list of available algorithms, and use `none` to set no preference at all. This allows the user to safely override the algorithm chosen by the recipient key preferences, as GPG will only select an algorithm that is usable by all recipients. The most highly ranked compression algorithm in this list is also used when there are no recipient keys to consider (e.g. ‘`--symmetric`’).

--s2k-cipher-algo *name*

Use *name* as the cipher algorithm for symmetric encryption with a passphrase if ‘--personal-cipher-preferences’ and ‘--cipher-algo’ are not given. The default is AES-128.

--s2k-digest-algo *name*

Use *name* as the digest algorithm used to mangle the passphrases for symmetric encryption. The default is SHA-1.

--s2k-mode *n*

Selects how passphrases for symmetric encryption are mangled. If *n* is 0 a plain passphrase (which is in general not recommended) will be used, a 1 adds a salt (which should not be used) to the passphrase and a 3 (the default) iterates the whole process a number of times (see ‘--s2k-count’).

--s2k-count *n*

Specify how many times the passphrases mangling for symmetric encryption is repeated. This value may range between 1024 and 65011712 inclusive. The default is inquired from gpg-agent. Note that not all values in the 1024-65011712 range are legal and if an illegal value is selected, GnuPG will round up to the nearest legal value. This option is only meaningful if ‘--s2k-mode’ is set to the default of 3.

4.2.5 Compliance options

These options control what GnuPG is compliant to. Only one of these options may be active at a time. Note that the default setting of this is nearly always the correct one. See the INTEROPERABILITY WITH OTHER OPENPGP PROGRAMS section below before using one of these options.

--gnupg Use standard GnuPG behavior. This is essentially OpenPGP behavior (see ‘--openpgp’), but with some additional workarounds for common compatibility problems in different versions of PGP. This is the default option, so it is not generally needed, but it may be useful to override a different compliance option in the gpg.conf file.

--openpgp

Reset all packet, cipher and digest options to strict OpenPGP behavior. Use this option to reset all previous options like ‘--s2k-*’, ‘--cipher-algo’, ‘--digest-algo’ and ‘--compress-algo’ to OpenPGP compliant values. All PGP workarounds are disabled.

--rfc4880

Reset all packet, cipher and digest options to strict RFC-4880 behavior. Note that this is currently the same thing as ‘--openpgp’.

--rfc4880bis

Enable experimental features from proposed updates to RFC-4880. This option can be used in addition to the other compliance options. Warning: The behavior may change with any GnuPG release and created keys or data may not be usable with future GnuPG versions.

- rfc2440** Reset all packet, cipher and digest options to strict RFC-2440 behavior. Note that by using this option encryption packets are created in a legacy mode without MDC protection. This is dangerous and should thus only be used for experiments. See also option '**--ignore-mdc-error**'.
- pgp6** Set up all options to be as PGP 6 compliant as possible. This restricts you to the ciphers IDEA (if the IDEA plugin is installed), 3DES, and CAST5, the hashes MD5, SHA1 and RIPEMD160, and the compression algorithms none and ZIP. This also disables '**--throw-keyids**', and making signatures with signing subkeys as PGP 6 does not understand signatures made by signing subkeys. This option implies '**--escape-from-lines**'.
- pgp7** Set up all options to be as PGP 7 compliant as possible. This is identical to '**--pgp6**' except that MDCs are not disabled, and the list of allowable ciphers is expanded to add AES128, AES192, AES256, and TWOFISH.
- pgp8** Set up all options to be as PGP 8 compliant as possible. PGP 8 is a lot closer to the OpenPGP standard than previous versions of PGP, so all this does is disable '**--throw-keyids**' and set '**--escape-from-lines**'. All algorithms are allowed except for the SHA224, SHA384, and SHA512 digests.
- compliance *string*** This option can be used instead of one of the options above. Valid values for *string* are the above option names (without the double dash) and possibly others as shown when using "help" for *value*.

4.2.6 Doing things one usually doesn't want to do

- n**
- dry-run** Don't make any changes (this is not completely implemented).
- list-only** Changes the behaviour of some commands. This is like '**--dry-run**' but different in some cases. The semantic of this option may be extended in the future. Currently it only skips the actual decryption pass and therefore enables a fast listing of the encryption keys.
- i**
- interactive** Prompt before overwriting any files.
- debug-level *level*** Select the debug level for investigating problems. *level* may be a numeric value or by a keyword:
- | | |
|--------------|--|
| none | No debugging at all. A value of less than 1 may be used instead of the keyword. |
| basic | Some basic debug messages. A value between 1 and 2 may be used instead of the keyword. |

- advanced** More verbose debug messages. A value between 3 and 5 may be used instead of the keyword.
- expert** Even more detailed messages. A value between 6 and 8 may be used instead of the keyword.
- guru** All of the debug messages you can get. A value greater than 8 may be used instead of the keyword. The creation of hash tracing files is only enabled if the keyword is used.

How these messages are mapped to the actual debugging flags is not specified and may change with newer releases of this program. They are however carefully selected to best aid in debugging.

--debug *flags*

Set debugging flags. All flags are or-ed and *flags* may be given in C syntax (e.g. 0x0042) or as a comma separated list of flag names. To get a list of all supported flags the single word "help" can be used.

--debug-all

Set all useful debugging flags.

--debug-iolbf

Set stdout into line buffered mode. This option is only honored when given on the command line.

--faked-system-time *epoch*

This option is only useful for testing; it sets the system time back or forth to *epoch* which is the number of seconds elapsed since the year 1970. Alternatively *epoch* may be given as a full ISO time string (e.g. "20070924T154812").

If you suffix *epoch* with an exclamation mark (!), the system time will appear to be frozen at the specified time.

--enable-progress-filter

Enable certain PROGRESS status outputs. This option allows frontends to display a progress indicator while gpg is processing larger files. There is a slight performance overhead using it.

--status-fd *n*

Write special status strings to the file descriptor *n*. See the file DETAILS in the documentation for a listing of them.

--status-file *file*

Same as '--status-fd', except the status data is written to file *file*.

--logger-fd *n*

Write log output to file descriptor *n* and not to STDERR.

--log-file *file*

--logger-file *file*

Same as '--logger-fd', except the logger data is written to file *file*. Use 'socket:/' to log to a socket. Note that in this version of gpg the option has only an effect if '--batch' is also used.

--attribute-fd *n*

Write attribute subpackets to the file descriptor *n*. This is most useful for use with '**--status-fd**', since the status messages are needed to separate out the various subpackets from the stream delivered to the file descriptor.

--attribute-file *file*

Same as '**--attribute-fd**', except the attribute data is written to file *file*.

--comment *string***--no-comments**

Use *string* as a comment string in cleartext signatures and ASCII armored messages or keys (see '**--armor**'). The default behavior is not to use a comment string. '**--comment**' may be repeated multiple times to get multiple comment strings. '**--no-comments**' removes all comments. It is a good idea to keep the length of a single comment below 60 characters to avoid problems with mail programs wrapping such lines. Note that comment lines, like all other header lines, are not protected by the signature.

--emit-version**--no-emit-version**

Force inclusion of the version string in ASCII armored output. If given once only the name of the program and the major number is emitted, given twice the minor is also emitted, given thrice the micro is added, and given four times an operating system identification is also emitted. '**--no-emit-version**' (default) disables the version line.

--sig-notation {*name=value*}**--cert-notation {*name=value*}****-N, --set-notation {*name=value*}**

Put the name value pair into the signature as notation data. *name* must consist only of printable characters or spaces, and must contain a '@' character in the form keyname@domain.example.com (substituting the appropriate keyname and domain name, of course). This is to help prevent pollution of the IETF reserved notation namespace. The '**--expert**' flag overrides the '@' check. *value* may be any printable string; it will be encoded in UTF-8, so you should check that your '**--display-charset**' is set correctly. If you prefix *name* with an exclamation mark (!), the notation data will be flagged as critical (rfc4880:5.2.3.16). '**--sig-notation**' sets a notation for data signatures. '**--cert-notation**' sets a notation for key signatures (certifications). '**--set-notation**' sets both.

There are special codes that may be used in notation names. "%k" will be expanded into the key ID of the key being signed, "%K" into the long key ID of the key being signed, "%f" into the fingerprint of the key being signed, "%s" into the key ID of the key making the signature, "%S" into the long key ID of the key making the signature, "%g" into the fingerprint of the key making the signature (which might be a subkey), "%p" into the fingerprint of the primary key of the key making the signature, "%c" into the signature count from the OpenPGP smartcard, and "%%" results in a single "%". %k, %K, and %f are

only meaningful when making a key signature (certification), and %c is only meaningful when using the OpenPGP smartcard.

--known-notation *name*

Adds *name* to a list of known critical signature notations. The effect of this is that gpg will not mark a signature with a critical signature notation of that name as bad. Note that gpg already knows by default about a few critical signatures notation names.

--sig-policy-url *string*

--cert-policy-url *string*

--set-policy-url *string*

Use *string* as a Policy URL for signatures (rfc4880:5.2.3.20). If you prefix it with an exclamation mark (!), the policy URL packet will be flagged as critical. ‘--sig-policy-url’ sets a policy url for data signatures. ‘--cert-policy-url’ sets a policy url for key signatures (certifications). ‘--set-policy-url’ sets both.

The same %-expandos used for notation data are available here as well.

--sig-keyserver-url *string*

Use *string* as a preferred keyserver URL for data signatures. If you prefix it with an exclamation mark (!), the keyserver URL packet will be flagged as critical.

The same %-expandos used for notation data are available here as well.

--set-filename *string*

Use *string* as the filename which is stored inside messages. This overrides the default, which is to use the actual filename of the file being encrypted. Using the empty string for *string* effectively removes the filename from the output.

--for-your-eyes-only

--no-for-your-eyes-only

Set the ‘for your eyes only’ flag in the message. This causes GnuPG to refuse to save the file unless the ‘--output’ option is given, and PGP to use a "secure viewer" with a claimed Tempest-resistant font to display the message. This option overrides ‘--set-filename’. ‘--no-for-your-eyes-only’ disables this option.

--use-embedded-filename

--no-use-embedded-filename

Try to create a file with a name as embedded in the data. This can be a dangerous option as it enables overwriting files. Defaults to no. Note that the option ‘--output’ overrides this option.

--cipher-algo *name*

Use *name* as cipher algorithm. Running the program with the command ‘--version’ yields a list of supported algorithms. If this is not used the cipher algorithm is selected from the preferences stored with the key. In general, you do not want to use this option as it allows you to violate the OpenPGP standard. ‘--personal-cipher-preferences’ is the safe way to accomplish the same thing.

--digest-algo *name*

Use *name* as the message digest algorithm. Running the program with the command '**--version**' yields a list of supported algorithms. In general, you do not want to use this option as it allows you to violate the OpenPGP standard. '**--personal-digest-preferences**' is the safe way to accomplish the same thing.

--compress-algo *name*

Use compression algorithm *name*. "zlib" is RFC-1950 ZLIB compression. "zip" is RFC-1951 ZIP compression which is used by PGP. "bzip2" is a more modern compression scheme that can compress some things better than zip or zlib, but at the cost of more memory used during compression and decompression. "uncompressed" or "none" disables compression. If this option is not used, the default behavior is to examine the recipient key preferences to see which algorithms the recipient supports. If all else fails, ZIP is used for maximum compatibility.

ZLIB may give better compression results than ZIP, as the compression window size is not limited to 8k. BZIP2 may give even better compression results than that, but will use a significantly larger amount of memory while compressing and decompressing. This may be significant in low memory situations. Note, however, that PGP (all versions) only supports ZIP compression. Using any algorithm other than ZIP or "none" will make the message unreadable with PGP. In general, you do not want to use this option as it allows you to violate the OpenPGP standard. '**--personal-compress-preferences**' is the safe way to accomplish the same thing.

--cert-digest-algo *name*

Use *name* as the message digest algorithm used when signing a key. Running the program with the command '**--version**' yields a list of supported algorithms. Be aware that if you choose an algorithm that GnuPG supports but other OpenPGP implementations do not, then some users will not be able to use the key signatures you make, or quite possibly your entire key.

--disable-cipher-algo *name*

Never allow the use of *name* as cipher algorithm. The given name will not be checked so that a later loaded algorithm will still get disabled.

--disable-pubkey-algo *name*

Never allow the use of *name* as public key algorithm. The given name will not be checked so that a later loaded algorithm will still get disabled.

--throw-keyids**--no-throw-keyids**

Do not put the recipient key IDs into encrypted messages. This helps to hide the receivers of the message and is a limited countermeasure against traffic analysis.¹ On the receiving side, it may slow down the decryption process because all available secret keys must be tried. '**--no-throw-keyids**' disables

¹ Using a little social engineering anyone who is able to decrypt the message can check whether one of the other recipients is the one he suspects.

this option. This option is essentially the same as using ‘`--hidden-recipient`’ for all recipients.

`--not-dash-escaped`

This option changes the behavior of cleartext signatures so that they can be used for patch files. You should not send such an armored file via email because all spaces and line endings are hashed too. You can not use this option for data which has 5 dashes at the beginning of a line, patch files don’t have this. A special armor header line tells GnuPG about this cleartext signature option.

`--escape-from-lines`

`--no-escape-from-lines`

Because some mailers change lines starting with "From " to ">From " it is good to handle such lines in a special way when creating cleartext signatures to prevent the mail system from breaking the signature. Note that all other PGP versions do it this way too. Enabled by default. ‘`--no-escape-from-lines`’ disables this option.

`--passphrase-repeat n`

Specify how many times `gpg2` will request a new passphrase be repeated. This is useful for helping memorize a passphrase. Defaults to 1 repetition; can be set to 0 to disable any passphrase repetition. Note that a *n* greater than 1 will pop up the pinentry window *n*+1 times even if a modern pinentry with two entry fields is used.

`--passphrase-fd n`

Read the passphrase from file descriptor *n*. Only the first line will be read from file descriptor *n*. If you use 0 for *n*, the passphrase will be read from STDIN. This can only be used if only one passphrase is supplied.

Note that since Version 2.0 this passphrase is only used if the option ‘`--batch`’ has also been given. Since Version 2.1 the ‘`--pinentry-mode`’ also needs to be set to `loopback`.

`--passphrase-file file`

Read the passphrase from file *file*. Only the first line will be read from file *file*. This can only be used if only one passphrase is supplied. Obviously, a passphrase stored in a file is of questionable security if other users can read this file. Don’t use this option if you can avoid it.

Note that since Version 2.0 this passphrase is only used if the option ‘`--batch`’ has also been given. Since Version 2.1 the ‘`--pinentry-mode`’ also needs to be set to `loopback`.

`--passphrase string`

Use *string* as the passphrase. This can only be used if only one passphrase is supplied. Obviously, this is of very questionable security on a multi-user system. Don’t use this option if you can avoid it.

Note that since Version 2.0 this passphrase is only used if the option ‘`--batch`’ has also been given. Since Version 2.1 the ‘`--pinentry-mode`’ also needs to be set to `loopback`.

- pinentry-mode *mode***
 Set the pinentry mode to *mode*. Allowed values for *mode* are:
- default Use the default of the agent, which is **ask**.
 - ask Force the use of the Pinentry.
 - cancel Emulate use of Pinentry's cancel button.
 - error Return a Pinentry error ("No Pinentry").
 - loopback Redirect Pinentry queries to the caller. Note that in contrast to Pinentry the user is not prompted again if he enters a bad password.
- no-symkey-cache**
 Disable the passphrase cache used for symmetrical en- and decryption. This cache is based on the message specific salt value (cf. '**--s2k-mode**').
- request-origin *origin***
 Tell gpg to assume that the operation ultimately originated at *origin*. Depending on the origin certain restrictions are applied and the Pinentry may include an extra note on the origin. Supported values for *origin* are: **local** which is the default, **remote** to indicate a remote origin or **browser** for an operation requested by a web browser.
- command-fd *n***
 This is a replacement for the deprecated shared-memory IPC mode. If this option is enabled, user input on questions is not expected from the TTY but from the given file descriptor. It should be used together with '**--status-fd**'. See the file doc/DETAILS in the source distribution for details on how to use it.
- command-file *file***
 Same as '**--command-fd**', except the commands are read out of file *file*
- allow-non-selfsigned-uid**
--no-allow-non-selfsigned-uid
 Allow the import and use of keys with user IDs which are not self-signed. This is not recommended, as a non self-signed user ID is trivial to forge. '**--no-allow-non-selfsigned-uid**' disables.
- allow-freeform-uid**
 Disable all checks on the form of the user ID while generating a new one. This option should only be used in very special environments as it does not ensure the de-facto standard format of user IDs.
- ignore-time-conflict**
 GnuPG normally checks that the timestamps associated with keys and signatures have plausible values. However, sometimes a signature seems to be older than the key due to clock problems. This option makes these checks just a warning. See also '**--ignore-valid-from**' for timestamp issues on subkeys.
- ignore-valid-from**
 GnuPG normally does not select and use subkeys created in the future. This option allows the use of such keys and thus exhibits the pre-1.0.7 behaviour.

You should not use this option unless there is some clock problem. See also ‘`--ignore-time-conflict`’ for timestamp issues with signatures.

`--ignore-crc-error`

The ASCII armor used by OpenPGP is protected by a CRC checksum against transmission errors. Occasionally the CRC gets mangled somewhere on the transmission channel but the actual content (which is protected by the OpenPGP protocol anyway) is still okay. This option allows GnuPG to ignore CRC errors.

`--ignore-mdc-error`

This option changes a MDC integrity protection failure into a warning. It is required to decrypt old messages which did not use an MDC. It may also be useful if a message is partially garbled, but it is necessary to get as much data as possible out of that garbled message. Be aware that a missing or failed MDC can be an indication of an attack. Use with great caution; see also option ‘`--rfc2440`’.

`--allow-weak-digest-algos`

Signatures made with known-weak digest algorithms are normally rejected with an “invalid digest algorithm” message. This option allows the verification of signatures made with such weak algorithms. MD5 is the only digest algorithm considered weak by default. See also ‘`--weak-digest`’ to reject other digest algorithms.

`--weak-digest name`

Treat the specified digest algorithm as weak. Signatures made over weak digests algorithms are normally rejected. This option can be supplied multiple times if multiple algorithms should be considered weak. See also ‘`--allow-weak-digest-algos`’ to disable rejection of weak digests. MD5 is always considered weak, and does not need to be listed explicitly.

`--allow-weak-key-signatures`

To avoid a minor risk of collision attacks on third-party key signatures made using SHA-1, those key signatures are considered invalid. This options allows to override this restriction.

`--no-default-keyring`

Do not add the default keyrings to the list of keyrings. Note that GnuPG will not operate without any keyrings, so if you use this option and do not provide alternate keyrings via ‘`--keyring`’ or ‘`--secret-keyring`’, then GnuPG will still use the default public or secret keyrings.

`--no-keyring`

Do not use any keyring at all. This overrides the default and all options which specify keyrings.

`--skip-verify`

Skip the signature verification step. This may be used to make the decryption faster if the signature verification is not needed.

--with-key-data

Print key listings delimited by colons (like '**--with-colons**') and print the public key data.

--list-signatures**--list-sigs**

Same as '**--list-keys**', but the signatures are listed too. This command has the same effect as using '**--list-keys**' with '**--with-sig-list**'. Note that in contrast to '**--check-signatures**' the key signatures are not verified. This command can be used to create a list of signing keys missing in the local keyring; for example:

```
gpg --list-sigs --with-colons USERID | \
  awk -F: '$1=="sig" && $2=="?" {if($13){print $13}else{print $5}}'
```

--fast-list-mode

Changes the output of the list commands to work faster; this is achieved by leaving some parts empty. Some applications don't need the user ID and the trust information given in the listings. By using this options they can get a faster listing. The exact behaviour of this option may change in future versions. If you are missing some information, don't use this option.

--no-literal

This is not for normal use. Use the source to see for what it might be useful.

--set-filesize

This is not for normal use. Use the source to see for what it might be useful.

--show-session-key

Display the session key used for one message. See '**--override-session-key**' for the counterpart of this option.

We think that Key Escrow is a Bad Thing; however the user should have the freedom to decide whether to go to prison or to reveal the content of one specific message without compromising all messages ever encrypted for one secret key.

You can also use this option if you receive an encrypted message which is abusive or offensive, to prove to the administrators of the messaging system that the ciphertext transmitted corresponds to an inappropriate plaintext so they can take action against the offending user.

--override-session-key *string***--override-session-key-fd *fd***

Don't use the public key but the session key *string* respective the session key taken from the first line read from file descriptor *fd*. The format of this string is the same as the one printed by '**--show-session-key**'. This option is normally not used but comes handy in case someone forces you to reveal the content of an encrypted message; using this option you can do this without handing out the secret key. Note that using '**--override-session-key**' may reveal the session key to all local users via the global process table. Often it is useful to combine this option with '**--no-keyring**'.

--ask-sig-expire
--no-ask-sig-expire
 When making a data signature, prompt for an expiration time. If this option is not specified, the expiration time set via '**--default-sig-expire**' is used. '**--no-ask-sig-expire**' disables this option.

--default-sig-expire
 The default expiration time to use for signature expiration. Valid values are "0" for no expiration, a number followed by the letter d (for days), w (for weeks), m (for months), or y (for years) (for example "2m" for two months, or "5y" for five years), or an absolute date in the form YYYY-MM-DD. Defaults to "0".

--ask-cert-expire
--no-ask-cert-expire
 When making a key signature, prompt for an expiration time. If this option is not specified, the expiration time set via '**--default-cert-expire**' is used. '**--no-ask-cert-expire**' disables this option.

--default-cert-expire
 The default expiration time to use for key signature expiration. Valid values are "0" for no expiration, a number followed by the letter d (for days), w (for weeks), m (for months), or y (for years) (for example "2m" for two months, or "5y" for five years), or an absolute date in the form YYYY-MM-DD. Defaults to "0".

--default-new-key-algo *string*
 This option can be used to change the default algorithms for key generation. The *string* is similar to the arguments required for the command '**--quick-add-key**' but slightly different. For example the current default of "rsa2048/cert,sign+rsa2048/encr" (or "rsa3072") can be changed to the value of what we currently call future default, which is "ed25519/cert,sign+cv25519/encr". You need to consult the source code to learn the details. Note that the advanced key generation commands can always be used to specify a key algorithm directly.

--allow-secret-key-import
 This is an obsolete option and is not used anywhere.

--allow-multiple-messages
--no-allow-multiple-messages
 Allow processing of multiple OpenPGP messages contained in a single file or stream. Some programs that call GPG are not prepared to deal with multiple messages being processed together, so this option defaults to no. Note that versions of GPG prior to 1.4.7 always allowed multiple messages. Future versions of GnUPG will remove this option.
 Warning: Do not use this option unless you need it as a temporary workaround!

--enable-special-filenames
 This option enables a mode in which filenames of the form '-&n', where n is a non-negative decimal number, refer to the file descriptor n and not to a file with that name.

- `--no-expensive-trust-checks`
Experimental use only.
- `--preserve-permissions`
Don't change the permissions of a secret keyring back to user read/write only.
Use this option only if you really know what you are doing.
- `--default-preference-list string`
Set the list of default preferences to *string*. This preference list is used for new keys and becomes the default for "setpref" in the edit menu.
- `--default-keyserver-url name`
Set the default keyserver URL to *name*. This keyserver will be used as the keyserver URL when writing a new self-signature on a key, which includes key generation and changing preferences.
- `--list-config`
Display various internal configuration parameters of GnuPG. This option is intended for external programs that call GnuPG to perform tasks, and is thus not generally useful. See the file 'doc/DETAILS' in the source distribution for the details of which configuration items may be listed. '`--list-config`' is only usable with '`--with-colons`' set.
- `--list-gcrypt-config`
Display various internal configuration parameters of Libgcrypt.
- `--gpgconf-list`
This command is similar to '`--list-config`' but in general only internally used by the `gpgconf` tool.
- `--gpgconf-test`
This is more or less dummy action. However it parses the configuration file and returns with failure if the configuration file would prevent `gpg2` from startup. Thus it may be used to run a syntax check on the configuration file.

4.2.7 Deprecated options

- `--show-photos`
- `--no-show-photos`
Causes '`--list-keys`', '`--list-signatures`', '`--list-public-keys`', '`--list-secret-keys`', and verifying a signature to also display the photo ID attached to the key, if any. See also '`--photo-viewer`'. These options are deprecated. Use '`--list-options [no-]show-photos`' and/or '`--verify-options [no-]show-photos`' instead.
- `--show-keyring`
Display the keyring name at the head of key listings to show which keyring a given key resides on. This option is deprecated: use '`--list-options [no-]show-keyring`' instead.
- `--always-trust`
Identical to '`--trust-model always`'. This option is deprecated.

`--show-notation`
`--no-show-notation`
 Show signature notations in the ‘`--list-signatures`’ or ‘`--check-signatures`’ listings as well as when verifying a signature with a notation in it. These options are deprecated. Use ‘`--list-options [no-]show-notation`’ and/or ‘`--verify-options [no-]show-notation`’ instead.

`--show-policy-url`
`--no-show-policy-url`
 Show policy URLs in the ‘`--list-signatures`’ or ‘`--check-signatures`’ listings as well as when verifying a signature with a policy URL in it. These options are deprecated. Use ‘`--list-options [no-]show-policy-url`’ and/or ‘`--verify-options [no-]show-policy-url`’ instead.

4.3 Configuration files

There are a few configuration files to control certain aspects of `gpg2`’s operation. Unless noted, they are expected in the current home directory (see [\[option `--homedir`\], page 4](#)).

‘`gpg.conf`’

This is the standard configuration file read by `gpg2` on startup. It may contain any valid long option; the leading two dashes may not be entered and the option may not be abbreviated. This default name may be changed on the command line (see [\[gpg-option `--options`\], page 55](#)). You should backup this file.

Note that on larger installations, it is useful to put predefined files into the directory ‘`/etc/skel/.gnupg`’ so that newly created users start up with a working configuration. For existing users a small helper script is provided to create these files (see [Section 9.3 \[addgnupghome\], page 138](#)).

For internal purposes `gpg2` creates and maintains a few other files; They all live in the current home directory (see [\[option `--homedir`\], page 4](#)). Only the `gpg2` program may modify these files.

‘`~/.gnupg`’

This is the default home directory which is used if neither the environment variable `GNUPGHOME` nor the option ‘`--homedir`’ is given.

‘`~/.gnupg/pubring.gpg`’

The public keyring using a legacy format. You should backup this file.

If this file is not available, `gpg` defaults to the new keybox format and creates a file ‘`pubring.kbx`’ unless that file already exists in which case that file will also be used for OpenPGP keys.

Note that in the case that both files, ‘`pubring.gpg`’ and ‘`pubring.kbx`’ exists but the latter has no OpenPGP keys, the legacy file ‘`pubring.gpg`’ will be used. Take care: GnuPG versions before 2.1 will always use the file ‘`pubring.gpg`’ because they do not know about the new keybox format. In the case that you have to use GnuPG 1.4 to decrypt archived data you should keep this file.

‘`~/.gnupg/pubring.gpg.lock`’

The lock file for the public keyring.

`‘~/.gnupg/pubring.kbx’`

The public keyring using the new keybox format. This file is shared with `gpgsm`. You should backup this file. See above for the relation between this file and its predecessor.

To convert an existing `‘pubring.gpg’` file to the keybox format, you first backup the ownertrust values, then rename `‘pubring.gpg’` to `‘publickeys.backup’`, so it won't be recognized by any GnuPG version, run `import`, and finally restore the ownertrust values:

```
$ cd ~/.gnupg
$ gpg --export-ownertrust >otrust.lst
$ mv pubring.gpg publickeys.backup
$ gpg --import-options restore --import publickeys.backups
$ gpg --import-ownertrust otrust.lst
```

`‘~/.gnupg/pubring.kbx.lock’`

The lock file for `‘pubring.kbx’`.

`‘~/.gnupg/secring.gpg’`

The legacy secret keyring as used by GnuPG versions before 2.1. It is not used by GnuPG 2.1 and later. You may want to keep it in case you have to use GnuPG 1.4 to decrypt archived data.

`‘~/.gnupg/secring.gpg.lock’`

The lock file for the legacy secret keyring.

`‘~/.gnupg/.gpg-v21-migrated’`

File indicating that a migration to GnuPG 2.1 has been done.

`‘~/.gnupg/trustdb.gpg’`

The trust database. There is no need to backup this file; it is better to backup the ownertrust values (see [\[option `--export-ownertrust`\], page 41](#)).

`‘~/.gnupg/trustdb.gpg.lock’`

The lock file for the trust database.

`‘~/.gnupg/random_seed’`

A file used to preserve the state of the internal random pool.

`‘~/.gnupg/openpgp-revocs.d/’`

This is the directory where `gpg` stores pre-generated revocation certificates. The file name corresponds to the OpenPGP fingerprint of the respective key. It is suggested to backup those certificates and if the primary private key is not stored on the disk to move them to an external storage device. Anyone who can access these files is able to revoke the corresponding key. You may want to print them out. You should backup all files in this directory and take care to keep this backup closed away.

Operation is further controlled by a few environment variables:

HOME Used to locate the default home directory.

GNUPGHOME

If set directory used instead of "`~/gnupg`".

GPG_AGENT_INFO

This variable is obsolete; it was used by GnuPG versions before 2.1.

PINENTRY_USER_DATA

This value is passed via `gpg-agent` to `pinentry`. It is useful to convey extra information to a custom `pinentry`.

COLUMNS

LINE Used to size some displays to the full size of the screen.

LANGUAGE

Apart from its use by GNU, it is used in the W32 version to override the language selection done through the Registry. If used and set to a valid and available language name (*langid*), the file with the translation is loaded from *gpgdir/gnupg.nls/langid.mo*. Here *gpgdir* is the directory out of which the `gpg` binary has been loaded. If it can't be loaded the Registry is tried and as last resort the native Windows locale system is used.

When calling the `gpg-agent` component `gpg2` sends a set of environment variables to `gpg-agent`. The names of these variables can be listed using the command:

```
gpg-connect-agent 'getinfo std_env_names' /bye | awk '$1=="D" {print $2}'
```

4.4 Examples

```
gpg -se -r Bob file
    sign and encrypt for user Bob
```

```
gpg --clear-sign file
    make a cleartext signature
```

```
gpg -sb file
    make a detached signature
```

```
gpg -u 0x12345678 -sb file
    make a detached signature with the key 0x12345678
```

```
gpg --list-keys user_ID
    show keys
```

```
gpg --fingerprint user_ID
    show fingerprint
```

```
gpg --verify pgpfile
```

```
gpg --verify sigfile [datafile]
```

Verify the signature of the file but do not output the data unless requested. The second form is used for detached signatures, where **sigfile** is the detached signature (either ASCII armored or binary) and **datafile** are the signed data; if this is not given, the name of the file holding the signed data is constructed by cutting off the extension (`".asc"` or `".sig"`) of **sigfile** or by asking the user for the filename. If the option `--output` is also used the signed data is written to the file specified by that option; use `-` to write the signed data to stdout.

FILTER EXPRESSIONS

The options ‘--import-filter’ and ‘--export-filter’ use expressions with this syntax (square brackets indicate an optional part and curly braces a repetition, white space between the elements are allowed):

```
[lc] [{flag}] PROPNAME op VALUE [lc]
```

The name of a property (*PROPNAME*) may only consist of letters, digits and under-scores. The description for the filter type describes which properties are defined. If an undefined property is used it evaluates to the empty string. Unless otherwise noted, the *VALUE* must always be given and may not be the empty string. No quoting is defined for the value, thus the value may not contain the strings *&&* or *||*, which are used as logical connection operators. The flag *--* can be used to remove this restriction.

Numerical values are computed as long int; standard C notation applies. *lc* is the logical connection operator; either *&&* for a conjunction or *||* for a disjunction. A conjunction is assumed at the begin of an expression. Conjunctions have higher precedence than disjunctions. If *VALUE* starts with one of the characters used in any *op* a space after the *op* is required.

The supported operators (*op*) are:

<i>=~</i>	Substring must match.
<i>!~</i>	Substring must not match.
<i>=</i>	The full string must match.
<i><></i>	The full string must not match.
<i>==</i>	The numerical value must match.
<i>!=</i>	The numerical value must not match.
<i><=</i>	The numerical value of the field must be LE than the value.
<i><</i>	The numerical value of the field must be LT than the value.
<i>></i>	The numerical value of the field must be GT than the value.
<i>>=</i>	The numerical value of the field must be GE than the value.
<i>-le</i>	The string value of the field must be less or equal than the value.
<i>-lt</i>	The string value of the field must be less than the value.
<i>-gt</i>	The string value of the field must be greater than the value.
<i>-ge</i>	The string value of the field must be greater or equal than the value.
<i>-n</i>	True if value is not empty (no value allowed).
<i>-z</i>	True if value is empty (no value allowed).
<i>-t</i>	Alias for "PROPNAME != 0" (no value allowed).
<i>-f</i>	Alias for "PROPNAME == 0" (no value allowed).

Values for *flag* must be space separated. The supported flags are:

- *VALUE* spans to the end of the expression.
- c The string match in this part is done case-sensitive.

The filter options concatenate several specifications for a filter of the same type. For example the four options in this example:

```
--import-filter keep-uid="uid =~ Alfa"
--import-filter keep-uid="&& uid !~ Test"
--import-filter keep-uid="|| uid =~ Alpha"
--import-filter keep-uid="uid !~ Test"
```

which is equivalent to

```
--import-filter \
keep-uid="uid =~ Alfa" && uid !~ Test" || uid =~ Alpha" && "uid !~ Test"
```

imports only the user ids of a key containing the strings "Alfa" or "Alpha" but not the string "test".

RETURN VALUE

The program returns 0 if there are no severe errors, 1 if at least a signature was bad, and other error codes for fatal errors.

Note that signature verification requires exact knowledge of what has been signed and by whom it has been signed. Using only the return code is thus not an appropriate way to verify a signature by a script. Either make proper use of the status codes or use the `gpgv` tool which has been designed to make signature verification easy for scripts.

WARNINGS

Use a good password for your user account and make sure that all security issues are always fixed on your machine. Also employ diligent physical protection to your machine. Consider to use a good passphrase as a last resort protection to your secret key in the case your machine gets stolen. It is important that your secret key is never leaked. Using an easy to carry around token or smartcard with the secret key is often a advisable.

If you are going to verify detached signatures, make sure that the program knows about it; either give both filenames on the command line or use ‘-’ to specify STDIN.

For scripted or other unattended use of `gpg` make sure to use the machine-parseable interface and not the default interface which is intended for direct use by humans. The machine-parseable interface provides a stable and well documented API independent of the locale or future changes of `gpg`. To enable this interface use the options ‘`--with-colons`’ and ‘`--status-fd`’. For certain operations the option ‘`--command-fd`’ may come handy too. See this man page and the file ‘DETAILS’ for the specification of the interface. Note that the GnuPG “info” pages as well as the PDF version of the GnuPG manual features a chapter on unattended use of GnuPG. As an alternative the library `GPGME` can be used as a high-level abstraction on top of that interface.

INTEROPERABILITY WITH OTHER OPENPGP PROGRAMS

GnuPG tries to be a very flexible implementation of the OpenPGP standard. In particular, GnuPG implements many of the optional parts of the standard, such as the SHA-512 hash, and the ZLIB and BZIP2 compression algorithms. It is important to be aware that not all OpenPGP programs implement these optional algorithms and that by forcing their use via the ‘`--cipher-algo`’, ‘`--digest-algo`’, ‘`--cert-digest-algo`’, or ‘`--compress-algo`’ options in GnuPG, it is possible to create a perfectly valid OpenPGP message, but one that cannot be read by the intended recipient.

There are dozens of variations of OpenPGP programs available, and each supports a slightly different subset of these optional algorithms. For example, until recently, no (unhacked) version of PGP supported the BLOWFISH cipher algorithm. A message using BLOWFISH simply could not be read by a PGP user. By default, GnuPG uses the standard OpenPGP preferences system that will always do the right thing and create messages that are usable by all recipients, regardless of which OpenPGP program they use. Only override this safe default if you really know what you are doing.

If you absolutely must override the safe default, or if the preferences on a given key are invalid for some reason, you are far better off using the ‘`--pgp6`’, ‘`--pgp7`’, or ‘`--pgp8`’ options. These options are safe as they do not force any particular algorithms in violation of OpenPGP, but rather reduce the available algorithms to a "PGP-safe" list.

BUGS

On older systems this program should be installed as `setuid(root)`. This is necessary to lock memory pages. Locking memory pages prevents the operating system from writing memory pages (which may contain passphrases or other sensitive material) to disk. If you get no warning message about insecure memory your operating system supports locking without being root. The program drops root privileges as soon as locked memory is allocated.

Note also that some systems (especially laptops) have the ability to “suspend to disk” (also known as “safe sleep” or “hibernate”). This writes all memory to disk before going into a low power or even powered off mode. Unless measures are taken in the operating system to protect the saved memory, passphrases or other sensitive material may be recoverable from it later.

Before you report a bug you should first search the mailing list archives for similar problems and second check whether such a bug has already been reported to our bug tracker at <https://bugs.gnupg.org>.

4.5 Unattended Usage

`gpg2` is often used as a backend engine by other software. To help with this a machine interface has been defined to have an unambiguous way to do this. The options ‘`--status-fd`’ and ‘`--batch`’ are almost always required for this.

4.5.1 Programmatic use of GnuPG

Please consider using GPGME instead of calling `gpg2` directly. GPGME offers a stable, backend-independent interface for many cryptographic operations. It supports OpenPGP and S/MIME, and also allows interaction with various GnuPG components.

GPGME provides a C-API, and comes with bindings for C++, Qt, and Python. Bindings for other languages are available.

4.5.2 Ephemeral home directories

Sometimes you want to contain effects of some operation, for example you want to import a key to inspect it, but you do not want this key to be added to your keyring. In earlier versions of GnuPG, it was possible to specify alternate keyring files for both public and secret keys. In modern GnuPG versions, however, we changed how secret keys are stored in order to better protect secret key material, and it was not possible to preserve this interface.

The preferred way to do this is to use ephemeral home directories. This technique works across all versions of GnuPG.

Create a temporary directory, create (or copy) a configuration that meets your needs, make `gpg2` use this directory either using the environment variable `GNUPGHOME`, or the option `--homedir`. GPGME supports this too on a per-context basis, by modifying the engine info of contexts. Now execute whatever operation you like, import and export key material as necessary. Once finished, you can delete the directory. All GnuPG backend services that were started will detect this and shut down.

4.5.3 The quick key manipulation interface

Recent versions of GnuPG have an interface to manipulate keys without using the interactive command `--edit-key`. This interface was added mainly for the benefit of GPGME (please consider using GPGME, see the manual subsection “Programmatic use of GnuPG”). This interface is described in the subsection “How to manage your keys”.

4.5.4 Unattended key generation

The command `--generate-key` may be used along with the option `--batch` for unattended key generation. This is the most flexible way of generating keys, but it is also the most complex one. Consider using the quick key manipulation interface described in the previous subsection “The quick key manipulation interface”.

The parameters for the key are either read from stdin or given as a file on the command line. The format of the parameter file is as follows:

- Text only, line length is limited to about 1000 characters.
- UTF-8 encoding must be used to specify non-ASCII characters.
- Empty lines are ignored.
- Leading and trailing white space is ignored.
- A hash sign as the first non white space character indicates a comment line.
- Control statements are indicated by a leading percent sign, the arguments are separated by white space from the keyword.
- Parameters are specified by a keyword, followed by a colon. Arguments are separated by white space.

- The first parameter must be ‘Key-Type’; control statements may be placed anywhere.
- The order of the parameters does not matter except for ‘Key-Type’ which must be the first parameter. The parameters are only used for the generated keyblock (primary and subkeys); parameters from previous sets are not used. Some syntactical checks may be performed.
- Key generation takes place when either the end of the parameter file is reached, the next ‘Key-Type’ parameter is encountered or at the control statement ‘%commit’ is encountered.

Control statements:

%echo *text*

Print *text* as diagnostic.

%dry-run Suppress actual key generation (useful for syntax checking).

%commit Perform the key generation. Note that an implicit commit is done at the next Key-Type parameter.

%pubring *filename*

Do not write the key to the default or commandline given keyring but to *filename*. This must be given before the first commit to take place, duplicate specification of the same filename is ignored, the last filename before a commit is used. The filename is used until a new filename is used (at commit points) and all keys are written to that file. If a new filename is given, this file is created (and overwrites an existing one).

See the previous subsection “Ephemeral home directories” for a more robust way to contain side-effects.

%secring *filename*

This option is a no-op for GnuPG 2.1 and later.

See the previous subsection “Ephemeral home directories”.

%ask-passphrase

%no-ask-passphrase

This option is a no-op for GnuPG 2.1 and later.

%no-protection

Using this option allows the creation of keys without any passphrase protection.

This option is mainly intended for regression tests.

%transient-key

If given the keys are created using a faster and a somewhat less secure random number generator. This option may be used for keys which are only used for a short time and do not require full cryptographic strength. It takes only effect if used together with the control statement ‘%no-protection’.

General Parameters:

Key-Type: *algo*

Starts a new parameter block by giving the type of the primary key. The algorithm must be capable of signing. This is a required parameter. *algo* may

either be an OpenPGP algorithm number or a string with the algorithm name. The special value `'default'` may be used for *algo* to create the default key type; in this case a `'Key-Usage'` shall not be given and `'default'` also be used for `'Subkey-Type'`.

Key-Length: *nbits*

The requested length of the generated key in bits. The default is returned by running the command `'gpg2--gpgconf-list'`. For ECC keys this parameter is ignored.

Key-Curve: *curve*

The requested elliptic curve of the generated key. This is a required parameter for ECC keys. It is ignored for non-ECC keys.

Key-Grip: *hexstring*

This is optional and used to generate a CSR or certificate for an already existing key. Key-Length will be ignored when given.

Key-Usage: *usage-list*

Space or comma delimited list of key usages. Allowed values are `'encrypt'`, `'sign'`, and `'auth'`. This is used to generate the key flags. Please make sure that the algorithm is capable of this usage. Note that OpenPGP requires that all primary keys are capable of certification, so no matter what usage is given here, the `'cert'` flag will be on. If no `'Key-Usage'` is specified and the `'Key-Type'` is not `'default'`, all allowed usages for that particular algorithm are used; if it is not given but `'default'` is used the usage will be `'sign'`.

Subkey-Type: *algo*

This generates a secondary key (subkey). Currently only one subkey can be handled. See also `'Key-Type'` above.

Subkey-Length: *nbits*

Length of the secondary key (subkey) in bits. The default is returned by running the command `'gpg2--gpgconf-list'`.

Subkey-Curve: *curve*

Key curve for a subkey; similar to `'Key-Curve'`.

Subkey-Usage: *usage-list*

Key usage lists for a subkey; similar to `'Key-Usage'`.

Passphrase: *string*

If you want to specify a passphrase for the secret key, enter it here. Default is to use the Pinentry dialog to ask for a passphrase.

Name-Real: *name*

Name-Comment: *comment*

Name-Email: *email*

The three parts of a user name. Remember to use UTF-8 encoding here. If you don't give any of them, no user ID is created.

Expire-Date: *iso-date|(number[d|w|m|y])*

Set the expiration date for the key (and the subkey). It may either be entered in ISO date format (e.g. `"20000815T145012"`) or as number of days, weeks,

month or years after the creation date. The special notation "seconds=N" is also allowed to specify a number of seconds since creation. Without a letter days are assumed. Note that there is no check done on the overflow of the type used by OpenPGP for timestamps. Thus you better make sure that the given value make sense. Although OpenPGP works with time intervals, GnuPG uses an absolute value internally and thus the last year we can represent is 2105.

Creation-Date: *iso-date*

Set the creation date of the key as stored in the key information and which is also part of the fingerprint calculation. Either a date like "1986-04-26" or a full timestamp like "19860426T042640" may be used. The time is considered to be UTC. The special notation "seconds=N" may be used to directly specify a the number of seconds since Epoch (Unix time). If it is not given the current time is used.

Preferences: *string*

Set the cipher, hash, and compression preference values for this key. This expects the same type of string as the sub-command 'setpref' in the '--edit-key' menu.

Revoker: *algo:fpr* [sensitive]

Add a designated revoker to the generated key. Algo is the public key algorithm of the designated revoker (i.e. RSA=1, DSA=17, etc.) *fpr* is the fingerprint of the designated revoker. The optional 'sensitive' flag marks the designated revoker as sensitive information. Only v4 keys may be designated revokers.

Keyserver: *string*

This is an optional parameter that specifies the preferred keyserver URL for the key.

Handle: *string*

This is an optional parameter only used with the status lines KEY_CREATED and KEY_NOT_CREATED. *string* may be up to 100 characters and should not contain spaces. It is useful for batch key generation to associate a key parameter block with a status line.

Here is an example on how to create a key in an ephemeral home directory:

```
$ export GNUPGHOME="$(mktemp -d)"
$ cat >foo <<EOF
    %echo Generating a basic OpenPGP key
    Key-Type: DSA
    Key-Length: 1024
    Subkey-Type: ELG-E
    Subkey-Length: 1024
    Name-Real: Joe Tester
    Name-Comment: with stupid passphrase
    Name-Email: joe@foo.bar
    Expire-Date: 0
    Passphrase: abc
    # Do a commit here, so that we can later print "done" :-)
    %commit
    %echo done
EOF
```



```

$ gpg2
--batch --generate-key foo
[...]
$ gpg2
--list-secret-keys
/tmp/tmp.ONQxB74PEf/pubring.kbx
-----
sec   dsa1024 2016-12-16 [SCA]
      768E895903FC1C44045C8CB95EEBDB71E9E849D0
uid           [ultimate] Joe Tester (with stupid passphrase) <joe@foo.bar>
ssb   elg1024 2016-12-16 [E]

```

If you want to create a key with the default algorithms you would use these parameters:

```

%echo Generating a default key
Key-Type: default
Subkey-Type: default
Name-Real: Joe Tester
Name-Comment: with stupid passphrase
Name-Email: joe@foo.bar
Expire-Date: 0
Passphrase: abc
# Do a commit here, so that we can later print "done" :-)
%commit
%echo done

```


5 Invoking GPGSM

`gpgsm` is a tool similar to `gpg` to provide digital encryption and signing services on X.509 certificates and the CMS protocol. It is mainly used as a backend for S/MIME mail processing. `gpgsm` includes a full featured certificate management and complies with all rules defined for the German Sphinx project.

See [\[Option Index\]](#), page 197, for an index to GPGSM's commands and options.

5.1 Commands

Commands are not distinguished from options except for the fact that only one command is allowed.

5.1.1 Commands not specific to the function

- `--version`
Print the program version and licensing information. Note that you cannot abbreviate this command.
- `--help`, `-h`
Print a usage message summarizing the most useful command-line options. Note that you cannot abbreviate this command.
- `--warranty`
Print warranty information. Note that you cannot abbreviate this command.
- `--dump-options`
Print a list of all available options and commands. Note that you cannot abbreviate this command.

5.1.2 Commands to select the type of operation

- `--encrypt`
Perform an encryption. The keys the data is encrypted to must be set using the option '`--recipient`'.
- `--decrypt`
Perform a decryption; the type of input is automatically determined. It may either be in binary form or PEM encoded; automatic determination of base-64 encoding is not done.
- `--sign`
Create a digital signature. The key used is either the first one found in the keybox or those set with the '`--local-user`' option.
- `--verify`
Check a signature file for validity. Depending on the arguments a detached signature may also be checked.
- `--server`
Run in server mode and wait for commands on the `stdin`.
- `--call-dirmngr command [args]`
Behave as a Dirmngr client issuing the request *command* with the optional list of *args*. The output of the Dirmngr is printed `stdout`. Please note that file names given as arguments should have an absolute file name (i.e. commencing with `/`)

because they are passed verbatim to the Dirmngr and the working directory of the Dirmngr might not be the same as the one of this client. Currently it is not possible to pass data via stdin to the Dirmngr. *command* should not contain spaces.

This command is required for certain maintaining tasks of the dirmngr where a dirmngr must be able to call back to **gpgsm**. See the Dirmngr manual for details.

--call-protect-tool *arguments*

Certain maintenance operations are done by an external program call **gpg-protect-tool**; this is usually not installed in a directory listed in the PATH variable. This command provides a simple wrapper to access this tool. *arguments* are passed verbatim to this command; use '**--help**' to get a list of supported operations.

5.1.3 How to manage the certificates and keys

--generate-key

--gen-key

This command allows the creation of a certificate signing request or a self-signed certificate. It is commonly used along with the '**--output**' option to save the created CSR or certificate into a file. If used with the '**--batch**' a parameter file is used to create the CSR or certificate and it is further possible to create non-self-signed certificates.

--list-keys

-k List all available certificates stored in the local key database. Note that the displayed data might be reformatted for better human readability and illegal characters are replaced by safe substitutes.

--list-secret-keys

-K List all available certificates for which a corresponding a secret key is available.

--list-external-keys *pattern*

List certificates matching *pattern* using an external server. This utilizes the dirmngr service.

--list-chain

Same as '**--list-keys**' but also prints all keys making up the chain.

--dump-cert

--dump-keys

List all available certificates stored in the local key database using a format useful mainly for debugging.

--dump-chain

Same as '**--dump-keys**' but also prints all keys making up the chain.

--dump-secret-keys

List all available certificates for which a corresponding a secret key is available using a format useful mainly for debugging.

--dump-external-keys *pattern*

List certificates matching *pattern* using an external server. This utilizes the `dirmngr` service. It uses a format useful mainly for debugging.

--keydb-clear-some-cert-flags

This is a debugging aid to reset certain flags in the key database which are used to cache certain certificate stati. It is especially useful if a bad CRL or a weird running OCSF responder did accidentally revoke certificate. There is no security issue with this command because `gpgsm` always make sure that the validity of a certificate is checked right before it is used.

--delete-keys *pattern*

Delete the keys matching *pattern*. Note that there is no command to delete the secret part of the key directly. In case you need to do this, you should run the command `gpgsm --dump-secret-keys KEYID` before you delete the key, copy the string of hex-digits in the “keygrip” line and delete the file consisting of these hex-digits and the suffix `.key` from the ‘`private-keys-v1.d`’ directory below our GnuPG home directory (usually ‘`~/.gnupg`’).

--export [*pattern*]

Export all certificates stored in the Keybox or those specified by the optional *pattern*. Those pattern consist of a list of user ids (see [\[how-to-specify-a-user-id\]](#), page 129). When used along with the ‘`--armor`’ option a few informational lines are prepended before each block. There is one limitation: As there is no commonly agreed upon way to pack more than one certificate into an ASN.1 structure, the binary export (i.e. without using ‘`armor`’) works only for the export of one certificate. Thus it is required to specify a *pattern* which yields exactly one certificate. Ephemeral certificate are only exported if all *pattern* are given as fingerprints or keygrips.

--export-secret-key-p12 *key-id*

Export the private key and the certificate identified by *key-id* using the PKCS#12 format. When used with the `--armor` option a few informational lines are prepended to the output. Note, that the PKCS#12 format is not very secure and proper transport security should be used to convey the exported key. (See [\[option -p12-charset\]](#), page 103.)

--export-secret-key-p8 *key-id***--export-secret-key-raw *key-id***

Export the private key of the certificate identified by *key-id* with any encryption stripped. The `...-raw` command exports in PKCS#1 format; the `...-p8` command exports in PKCS#8 format. When used with the `--armor` option a few informational lines are prepended to the output. These commands are useful to prepare a key for use on a TLS server.

--import [*files*]

Import the certificates from the PEM or binary encoded files as well as from signed-only messages. This command may also be used to import a secret key from a PKCS#12 file.

--learn-card

Read information about the private keys from the smartcard and import the certificates from there. This command utilizes the `gpg-agent` and in turn the `scdaemon`.

--change-passphrase *user_id***--passwd *user_id***

Change the passphrase of the private key belonging to the certificate specified as *user_id*. Note, that changing the passphrase/PIN of a smartcard is not yet supported.

5.2 Option Summary

GPGSM features a bunch of options to control the exact behaviour and to change the default configuration.

5.2.1 How to change the configuration

These options are used to change the configuration and are usually found in the option file.

--options *file*

Reads configuration from *file* instead of from the default per-user configuration file. The default configuration file is named '`gpgsm.conf`' and expected in the '`.gnupg`' directory directly below the home directory of the user.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to '`~/gnupg`'. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable `GNUPGHOME` or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named '`gpgconf.ctl`' in the same directory as the tool '`gpgconf.exe`'. The root of the installation is then that directory; or, if '`gpgconf.exe`' has been installed directly below a directory named '`bin`', its parent directory. You also need to make sure that the following directories exist and are writable: '`ROOT/home`' for the GnuPG home and '`ROOT/var/cache/gnupg`' for internal cache files.

-v**--verbose**

Outputs additional information while running. You can increase the verbosity by giving several verbose commands to `gpgsm`, such as '`-vv`'.

--policy-file *filename*

Change the default name of the policy file to *filename*.

--agent-program *file*

Specify an agent program to be used for secret key operations. The default value is determined by running the command `gpgconf`. Note that the pipe symbol (`|`) is used for a regression test suite hack and may thus not be used in the file name.

--dirmngr-program *file*

Specify a dirmngr program to be used for CRL checks. The default value is `‘/usr/bin/dirmngr’`.

--prefer-system-dirmngr

This option is obsolete and ignored.

--disable-dirmngr

Entirely disable the use of the Dirmngr.

--no-autostart

Do not start the `gpg-agent` or the `dirmngr` if it has not yet been started and its service is required. This option is mostly useful on machines where the connection to `gpg-agent` has been redirected to another machines. If `dirmngr` is required on the remote machine, it may be started manually using `gpgconf --launch dirmngr`.

--no-secmem-warning

Do not print a warning when the so called "secure memory" cannot be used.

--log-file *file*

When running in server mode, append all logging output to *file*. Use `‘socket:/'` to log to socket.

5.2.2 Certificate related options

--enable-policy-checks**--disable-policy-checks**

By default policy checks are enabled. These options may be used to change it.

--enable-crl-checks**--disable-crl-checks**

By default the CRL checks are enabled and the `DirMngr` is used to check for revoked certificates. The disable option is most useful with an off-line network connection to suppress this check and also to avoid that new certificates introduce a web bug by including a certificate specific CRL DP. The disable option also disables an issuer certificate lookup via the `authorityInfoAccess` property of the certificate; the `‘--enable-issuer-key-retrieve’` can be used to make use of that property anyway.

--enable-trusted-cert-crl-check**--disable-trusted-cert-crl-check**

By default the CRL for trusted root certificates are checked like for any other certificates. This allows a CA to revoke its own certificates voluntarily without the need of putting all ever issued certificates into a CRL. The disable option may be used to switch this extra check off. Due to the caching done by the

Dirmngr, there will not be any noticeable performance gain. Note, that this also disables possible OCSP checks for trusted root certificates. A more specific way of disabling this check is by adding the “relax” keyword to the root CA line of the ‘`trustlist.txt`’

--force-crl-refresh

Tell the dirmngr to reload the CRL for each request. For better performance, the dirmngr will actually optimize this by suppressing the loading for short time intervals (e.g. 30 minutes). This option is useful to make sure that a fresh CRL is available for certificates hold in the keybox. The suggested way of doing this is by using it along with the option ‘`--with-validation`’ for a key listing command. This option should not be used in a configuration file.

--enable-issuer-based-crl-check

Run a CRL check even for certificates which do not have any CRL distribution point. This requires that a suitable LDAP server has been configured in Dirmngr and that the CRL can be found using the issuer. This option reverts to what GnuPG did up to version 2.2.20. This option is in general not useful.

--enable-ocsp

--disable-ocsp

By default OCSP checks are disabled. The enable option may be used to enable OCSP checks via Dirmngr. If CRL checks are also enabled, CRLs will be used as a fallback if for some reason an OCSP request will not succeed. Note, that you have to allow OCSP requests in Dirmngr’s configuration too (option ‘`--allow-ocsp`’) and configure Dirmngr properly. If you do not do so you will get the error code ‘`Not supported`’.

--auto-issuer-key-retrieve

If a required certificate is missing while validating the chain of certificates, try to load that certificate from an external location. This usually means that Dirmngr is employed to search for the certificate. Note that this option makes a “web bug” like behavior possible. LDAP server operators can see which keys you request, so by sending you a message signed by a brand new key (which you naturally will not have on your local keybox), the operator can tell both your IP address and the time when you verified the signature.

--validation-model *name*

This option changes the default validation model. The only possible values are “shell” (which is the default), “chain” which forces the use of the chain model and “steed” for a new simplified model. The chain model is also used if an option in the ‘`trustlist.txt`’ or an attribute of the certificate requests it. However the standard model (shell) is in that case always tried first.

--ignore-cert-extension *oid*

Add *oid* to the list of ignored certificate extensions. The *oid* is expected to be in dotted decimal form, like 2.5.29.3. This option may be used more than once. Critical flagged certificate extensions matching one of the OIDs in the list are treated as if they are actually handled and thus the certificate will not be rejected due to an unknown critical extension. Use this option with care because extensions are usually flagged as critical for a reason.

5.2.3 Input and Output

--armor
-a Create PEM encoded output. Default is binary output.

--base64 Create Base-64 encoded output; i.e. PEM without the header lines.

--assume-armor
Assume the input data is PEM encoded. Default is to autodetect the encoding but this may fail.

--assume-base64
Assume the input data is plain base-64 encoded.

--assume-binary
Assume the input data is binary encoded.

--p12-charset *name*
gpgsm uses the UTF-8 encoding when encoding passphrases for PKCS#12 files. This option may be used to force the passphrase to be encoded in the specified encoding *name*. This is useful if the application used to import the key uses a different encoding and thus will not be able to import a file generated by gpgsm. Commonly used values for *name* are `Latin1` and `CP850`. Note that gpgsm itself automatically imports any file with a passphrase encoded to the most commonly used encodings.

--default-key *user_id*
Use *user_id* as the standard key for signing. This key is used if no other key has been defined as a signing key. Note, that the first '**--local-users**' option also sets this key if it has not yet been set; however '**--default-key**' always overrides this.

--local-user *user_id*
-u *user_id*
Set the user(s) to be used for signing. The default is the first secret key found in the database.

--recipient *name*
-r Encrypt to the user id *name*. There are several ways a user id may be given (see [\[how-to-specify-a-user-id\]](#), page 129).

--output *file*
-o *file* Write output to *file*. The default is to write it to stdout.

--with-key-data
Displays extra information with the **--list-keys** commands. Especially a line tagged **grp** is printed which tells you the keygrip of a key. This string is for example used as the file name of the secret key. Implies **--with-colons**.

--with-validation
When doing a key listing, do a full validation check for each key and print the result. This is usually a slow operation because it requires a CRL lookup and other operations.

When used along with ‘`--import`’, a validation of the certificate to import is done and only imported if it succeeds the test. Note that this does not affect an already available certificate in the DB. This option is therefore useful to simply verify a certificate.

`--with-md5-fingerprint`

For standard key listings, also print the MD5 fingerprint of the certificate.

`--with-keygrip`

Include the keygrip in standard key listings. Note that the keygrip is always listed in ‘`--with-colons`’ mode.

`--with-secret`

Include info about the presence of a secret key in public key listings done with `--with-colons`.

5.2.4 How to change how the CMS is created

`--include-certs n`

Using *n* of -2 includes all certificate except for the root cert, -1 includes all certs, 0 does not include any certs, 1 includes only the signers cert and all other positive values include up to *n* certificates starting with the signer cert. The default is -2.

`--cipher-algo oid`

Use the cipher algorithm with the ASN.1 object identifier *oid* for encryption. For convenience the strings 3DES, AES and AES256 may be used instead of their OIDs. The default is AES (2.16.840.1.101.3.4.1.2).

`--digest-algo name`

Use *name* as the message digest algorithm. Usually this algorithm is deduced from the respective signing certificate. This option forces the use of the given algorithm and may lead to severe interoperability problems.

5.2.5 Doing things one usually do not want to do

`--extra-digest-algo name`

Sometimes signatures are broken in that they announce a different digest algorithm than actually used. `gpgsm` uses a one-pass data processing model and thus needs to rely on the announced digest algorithms to properly hash the data. As a workaround this option may be used to tell `gpgsm` to also hash the data using the algorithm *name*; this slows processing down a little bit but allows verification of such broken signatures. If `gpgsm` prints an error like “digest algo 8 has not been enabled” you may want to try this option, with ‘SHA256’ for *name*.

`--faked-system-time epoch`

This option is only useful for testing; it sets the system time back or forth to *epoch* which is the number of seconds elapsed since the year 1970. Alternatively *epoch* may be given as a full ISO time string (e.g. "20070924T154812").

--with-ephemeral-keys

Include ephemeral flagged keys in the output of key listings. Note that they are included anyway if the key specification for a listing is given as fingerprint or keygrip.

--debug-level *level*

Select the debug level for investigating problems. *level* may be a numeric value or by a keyword:

none	No debugging at all. A value of less than 1 may be used instead of the keyword.
basic	Some basic debug messages. A value between 1 and 2 may be used instead of the keyword.
advanced	More verbose debug messages. A value between 3 and 5 may be used instead of the keyword.
expert	Even more detailed messages. A value between 6 and 8 may be used instead of the keyword.
guru	All of the debug messages you can get. A value greater than 8 may be used instead of the keyword. The creation of hash tracing files is only enabled if the keyword is used.

How these messages are mapped to the actual debugging flags is not specified and may change with newer releases of this program. They are however carefully selected to best aid in debugging.

--debug *flags*

This option is only useful for debugging and the behaviour may change at any time without notice; using **--debug-levels** is the preferred method to select the debug verbosity. **FLAGS** are bit encoded and may be given in usual C-Syntax. The currently defined bits are:

0 (1)	X.509 or OpenPGP protocol related data
1 (2)	values of big number integers
2 (4)	low level crypto operations
5 (32)	memory allocation
6 (64)	caching
7 (128)	show memory statistics
9 (512)	write hashed data to files named dbgmd-000*
10 (1024)	trace Assuan protocol

Note, that all flags set using this option may get overridden by **--debug-level**.

--debug-all

Same as **--debug=0xffffffff**

--debug-allow-core-dump

Usually **gpgsm** tries to avoid dumping core by well written code and by disabling core dumps for security reasons. However, bugs are pretty durable beasts and to squash them it is sometimes useful to have a core dump. This option enables core dumps unless the Bad Thing happened before the option parsing.

--debug-no-chain-validation

This is actually not a debugging option but only useful as such. It lets **gpgsm** bypass all certificate chain validation checks.

--debug-ignore-expiration

This is actually not a debugging option but only useful as such. It lets **gpgsm** ignore all notAfter dates, this is used by the regression tests.

--passphrase-fd n

Read the passphrase from file descriptor **n**. Only the first line will be read from file descriptor **n**. If you use 0 for **n**, the passphrase will be read from STDIN. This can only be used if only one passphrase is supplied.

Note that this passphrase is only used if the option ‘**--batch**’ has also been given.

--pinentry-mode mode

Set the pinentry mode to **mode**. Allowed values for **mode** are:

default	Use the default of the agent, which is ask .
ask	Force the use of the Pinentry.
cancel	Emulate use of Pinentry’s cancel button.
error	Return a Pinentry error (“No Pinentry”).
loopback	Redirect Pinentry queries to the caller. Note that in contrast to Pinentry the user is not prompted again if he enters a bad password.

--request-origin origin

Tell **gpgsm** to assume that the operation ultimately originated at *origin*. Depending on the origin certain restrictions are applied and the Pinentry may include an extra note on the origin. Supported values for *origin* are: **local** which is the default, **remote** to indicate a remote origin or **browser** for an operation requested by a web browser.

--no-common-certs-import

Suppress the import of common certificates on keybox creation.

All the long options may also be given in the configuration file after stripping off the two leading dashes.

5.3 Configuration files

There are a few configuration files to control certain aspects of **gpgsm**’s operation. Unless noted, they are expected in the current home directory (see [\[option **--homedir**, page 4\]](#)).

`'gpgsm.conf'`

This is the standard configuration file read by `gpgsm` on startup. It may contain any valid long option; the leading two dashes may not be entered and the option may not be abbreviated. This default name may be changed on the command line (see [\[gpgsm-option -options\]](#), page 100). You should backup this file.

`'policies.txt'`

This is a list of allowed CA policies. This file should list the object identifiers of the policies line by line. Empty lines and lines starting with a hash mark are ignored. Policies missing in this file and not marked as critical in the certificate will print only a warning; certificates with policies marked as critical and not listed in this file will fail the signature verification. You should backup this file.

For example, to allow only the policy 2.289.9.9, the file should look like this:

```
# Allowed policies
2.289.9.9
```

`'qualified.txt'`

This is the list of root certificates used for qualified certificates. They are defined as certificates capable of creating legally binding signatures in the same way as handwritten signatures are. Comments start with a hash mark and empty lines are ignored. Lines do have a length limit but this is not a serious limitation as the format of the entries is fixed and checked by `gpgsm`: A non-comment line starts with optional whitespace, followed by exactly 40 hex characters, white space and a lowercased 2 letter country code. Additional data delimited with by a white space is current ignored but might later be used for other purposes.

Note that even if a certificate is listed in this file, this does not mean that the certificate is trusted; in general the certificates listed in this file need to be listed also in `'trustlist.txt'`.

This is a global file installed in the data directory (e.g. `'/usr/share/gnupg/qualified.txt'`). GnuPG installs a suitable file with root certificates as used in Germany. As new Root-CA certificates may be issued over time, these entries may need to be updated; new distributions of this software should come with an updated list but it is still the responsibility of the Administrator to check that this list is correct.

Every time `gpgsm` uses a certificate for signing or verification this file will be consulted to check whether the certificate under question has ultimately been issued by one of these CAs. If this is the case the user will be informed that the verified signature represents a legally binding (“qualified”) signature. When creating a signature using such a certificate an extra prompt will be issued to let the user confirm that such a legally binding signature shall really be created.

Because this software has not yet been approved for use with such certificates, appropriate notices will be shown to indicate this fact.

`'help.txt'`

This is plain text file with a few help entries used with `pinentry` as well as a large list of help items for `gpg` and `gpgsm`. The standard file has English help texts; to install localized versions use filenames like `'help.LL.txt'` with

LL denoting the locale. GnuPG comes with a set of predefined help files in the data directory (e.g. `/usr/share/gnupg/gnupg/help.de.txt`) and allows overriding of any help item by help files stored in the system configuration directory (e.g. `/etc/gnupg/help.de.txt`). For a reference of the help file's syntax, please see the installed `help.txt` file.

`'com-certs.pem'`

This file is a collection of common certificates used to populated a newly created `'pubring.kbx'`. An administrator may replace this file with a custom one. The format is a concatenation of PEM encoded X.509 certificates. This global file is installed in the data directory (e.g. `/usr/share/gnupg/com-certs.pem`).

Note that on larger installations, it is useful to put predefined files into the directory `/etc/skel/.gnupg/` so that newly created users start up with a working configuration. For existing users a small helper script is provided to create these files (see [Section 9.3 \[addgnupghome\]](#), page 138).

For internal purposes `gpgsm` creates and maintains a few other files; they all live in the current home directory (see [\[option -homedir\]](#), page 4). Only `gpgsm` may modify these files.

`'pubring.kbx'`

This a database file storing the certificates as well as meta information. For debugging purposes the tool `kbxutil` may be used to show the internal structure of this file. You should backup this file.

`'random_seed'`

This content of this file is used to maintain the internal state of the random number generator across invocations. The same file is used by other programs of this software too.

`'S.gpg-agent'`

If this file exists `gpgsm` will first try to connect to this socket for accessing `gpg-agent` before starting a new `gpg-agent` instance. Under Windows this socket (which in reality be a plain file describing a regular TCP listening port) is the standard way of connecting the `gpg-agent`.

5.4 Examples

```
$ gpgsm -er goo@bar.net <plaintext >ciphertext
```

5.5 Unattended Usage

`gpgsm` is often used as a backend engine by other software. To help with this a machine interface has been defined to have an unambiguous way to do this. This is most likely used with the `--server` command but may also be used in the standard operation mode by using the `--status-fd` option.

5.5.1 Automated signature checking

It is very important to understand the semantics used with signature verification. Checking a signature is not as simple as it may sound and so the operation is a bit complicated. In most cases it is required to look at several status lines. Here is a table of all cases a signed message may have:

The signature is valid

This does mean that the signature has been successfully verified, the certificates are all sane. However there are two subcases with important information: One of the certificates may have expired or a signature of a message itself as expired. It is a sound practise to consider such a signature still as valid but additional information should be displayed. Depending on the subcase `gpgsm` will issue these status codes:

signature valid and nothing did expire

`GOODSIG, VALIDSIG, TRUST_FULLY`

signature valid but at least one certificate has expired

`EXPKEYSIG, VALIDSIG, TRUST_FULLY`

signature valid but expired

`EXPSIG, VALIDSIG, TRUST_FULLY` Note, that this case is currently not implemented.

The signature is invalid

This means that the signature verification failed (this is an indication of a transfer error, a program error or tampering with the message). `gpgsm` issues one of these status codes sequences:

`BADSIG`

`GOODSIG, VALIDSIG TRUST_NEVER`

Error verifying a signature

For some reason the signature could not be verified, i.e. it cannot be decided whether the signature is valid or invalid. A common reason for this is a missing certificate.

5.5.2 CSR and certificate creation

The command ‘`--generate-key`’ may be used along with the option ‘`--batch`’ to either create a certificate signing request (CSR) or an X.509 certificate. This is controlled by a parameter file; the format of this file is as follows:

- Text only, line length is limited to about 1000 characters.
- UTF-8 encoding must be used to specify non-ASCII characters.
- Empty lines are ignored.
- Leading and trailing while space is ignored.
- A hash sign as the first non white space character indicates a comment line.
- Control statements are indicated by a leading percent sign, the arguments are separated by white space from the keyword.
- Parameters are specified by a keyword, followed by a colon. Arguments are separated by white space.
- The first parameter must be ‘`Key-Type`’, control statements may be placed anywhere.
- The order of the parameters does not matter except for ‘`Key-Type`’ which must be the first parameter. The parameters are only used for the generated CSR/certificate; parameters from previous sets are not used. Some syntactically checks may be performed.

- Key generation takes place when either the end of the parameter file is reached, the next ‘Key-Type’ parameter is encountered or at the control statement ‘%commit’ is encountered.

Control statements:

%echo *text*

Print *text* as diagnostic.

%dry-run Suppress actual key generation (useful for syntax checking).

%commit Perform the key generation. Note that an implicit commit is done at the next Key-Type parameter.

General Parameters:

Key-Type: *algo*

Starts a new parameter block by giving the type of the primary key. The algorithm must be capable of signing. This is a required parameter. The only supported value for *algo* is ‘rsa’.

Key-Length: *nbits*

The requested length of a generated key in bits. Defaults to 3072.

Key-Grip: *hexstring*

This is optional and used to generate a CSR or certificate for an already existing key. Key-Length will be ignored when given.

Key-Usage: *usage-list*

Space or comma delimited list of key usage, allowed values are ‘encrypt’, ‘sign’ and ‘cert’. This is used to generate the keyUsage extension. Please make sure that the algorithm is capable of this usage. Default is to allow encrypt and sign.

Name-DN: *subject-name*

This is the Distinguished Name (DN) of the subject in RFC-2253 format.

Name-Email: *string*

This is an email address for the altSubjectName. This parameter is optional but may occur several times to add several email addresses to a certificate.

Name-DNS: *string*

This is a DNS name for the altSubjectName. This parameter is optional but may occur several times to add several DNS names to a certificate.

Name-URI: *string*

This is a URI for the altSubjectName. This parameter is optional but may occur several times to add several URIs to a certificate.

Additional parameters used to create a certificate (in contrast to a certificate signing request):

Serial: *sn* If this parameter is given an X.509 certificate will be generated. *sn* is expected to be a hex string representing an unsigned integer of arbitrary length. The special value ‘random’ can be used to create a 64 bit random serial number.

Issuer-DN: *issuer-name*

This is the DN name of the issuer in RFC-2253 format. If it is not set it will default to the subject DN and a special GnuPG extension will be included in the certificate to mark it as a standalone certificate.

Creation-Date: *iso-date*

Not-Before: *iso-date*

Set the notBefore date of the certificate. Either a date like ‘1986-04-26’ or ‘1986-04-26 12:00’ or a standard ISO timestamp like ‘19860426T042640’ may be used. The time is considered to be UTC. If it is not given the current date is used.

Expire-Date: *iso-date*

Not-After: *iso-date*

Set the notAfter date of the certificate. Either a date like ‘2063-04-05’ or ‘2063-04-05 17:00’ or a standard ISO timestamp like ‘20630405T170000’ may be used. The time is considered to be UTC. If it is not given a default value in the not too far future is used.

Signing-Key: *keygrip*

This gives the keygrip of the key used to sign the certificate. If it is not given a self-signed certificate will be created. For compatibility with future versions, it is suggested to prefix the keygrip with a ‘&’.

Hash-Algo: *hash-algo*

Use *hash-algo* for this CSR or certificate. The supported hash algorithms are: ‘sha1’, ‘sha256’, ‘sha384’ and ‘sha512’; they may also be specified with upper-case letters. The default is ‘sha256’.

5.6 The Protocol the Server Mode Uses

Description of the protocol used to access GPGSM. GPGSM does implement the Assuan protocol and in addition provides a regular command line interface which exhibits a full client to this protocol (but uses internal linking). To start **gpgsm** as a server the command line the option **--server** must be used. Additional options are provided to select the communication method (i.e. the name of the socket).

We assume that the connection has already been established; see the Assuan manual for details.

5.6.1 Encrypting a Message

Before encryption can be done the recipient must be set using the command:

RECIPIENT *userID*

Set the recipient for the encryption. *userID* should be the internal representation of the key; the server may accept any other way of specification. If this is a valid and trusted recipient the server does respond with OK, otherwise the return is an ERR with the reason why the recipient cannot be used, the encryption will then not be done for this recipient. If the policy is not to encrypt at all if not all recipients are valid, the client has to take care of this. All **RECIPIENT** commands are cumulative until a **RESET** or an successful **ENCRYPT** command.

```
INPUT FD[=n] [--armor|--base64|--binary]
```

Set the file descriptor for the message to be encrypted to *n*. Obviously the pipe must be open at that point, the server establishes its own end. If the server returns an error the client should consider this session failed. If *n* is not given, this commands uses the last file descriptor passed to the application. See [section “the `assuan_sendfd` function” in the *Libassuan manual*](#), on how to do descriptor passing.

The `--armor` option may be used to advise the server that the input data is in PEM format, `--base64` advises that a raw base-64 encoding is used, `--binary` advises of raw binary input (BER). If none of these options is used, the server tries to figure out the used encoding, but this may not always be correct.

```
OUTPUT FD[=n] [--armor|--base64]
```

Set the file descriptor to be used for the output (i.e. the encrypted message). Obviously the pipe must be open at that point, the server establishes its own end. If the server returns an error the client should consider this session failed.

The option `'--armor'` encodes the output in PEM format, the `'--base64'` option applies just a base-64 encoding. No option creates binary output (BER).

The actual encryption is done using the command

```
ENCRYPT
```

It takes the plaintext from the `INPUT` command, writes to the ciphertext to the file descriptor set with the `OUTPUT` command, take the recipients from all the recipients set so far. If this command fails the clients should try to delete all output currently done or otherwise mark it as invalid. `GP GSM` does ensure that there will not be any security problem with leftover data on the output in this case.

This command should in general not fail, as all necessary checks have been done while setting the recipients. The input and output pipes are closed.

5.6.2 Decrypting a message

Input and output FDs are set the same way as in encryption, but `INPUT` refers to the ciphertext and `OUTPUT` to the plaintext. There is no need to set recipients. `GP GSM` automatically strips any S/MIME headers from the input, so it is valid to pass an entire MIME part to the `INPUT` pipe.

The decryption is done by using the command

```
DECRYPT
```

It performs the decrypt operation after doing some check on the internal state (e.g. that all needed data has been set). Because it utilizes the GPG-Agent for the session key decryption, there is no need to ask the client for a protecting passphrase - GpgAgent takes care of this by requesting this from the user.

5.6.3 Signing a Message

Signing is usually done with these commands:

```
INPUT FD[=n] [--armor|--base64|--binary]
```

This tells `GP GSM` to read the data to sign from file descriptor *n*.

```
OUTPUT FD[=m] [--armor|--base64]
```

Write the output to file descriptor *m*. If a detached signature is requested, only the signature is written.

```
SIGN [--detached]
```

Sign the data set with the INPUT command and write it to the sink set by OUTPUT. With `--detached`, a detached signature is created (surprise).

The key used for signing is the default one or the one specified in the configuration file. To get finer control over the keys, it is possible to use the command

```
SIGNER userID
```

to set the signer's key. *userID* should be the internal representation of the key; the server may accept any other way of specification. If this is a valid and trusted recipient the server does respond with OK, otherwise the return is an ERR with the reason why the key cannot be used, the signature will then not be created using this key. If the policy is not to sign at all if not all keys are valid, the client has to take care of this. All **SIGNER** commands are cumulative until a **RESET** is done. Note that a **SIGN** does not reset this list of signers which is in contrast to the **RECIPIENT** command.

5.6.4 Verifying a Message

To verify a message the command:

```
VERIFY
```

is used. It does a verify operation on the message send to the input FD. The result is written out using status lines. If an output FD was given, the signed text will be written to that. If the signature is a detached one, the server will inquire about the signed material and the client must provide it.

5.6.5 Generating a Key

This is used to generate a new keypair, store the secret part in the PSE and the public key in the key database. We will probably add optional commands to allow the client to select whether a hardware token is used to store the key. Configuration options to GPGSM can be used to restrict the use of this command.

```
GENKEY
```

GPGSM checks whether this command is allowed and then does an **INQUIRY** to get the key parameters, the client should then send the key parameters in the native format:

```
S: INQUIRE KEY_PARAM native
C: D foo:fgfgfg
C: D bar
C: END
```

Please note that the server may send Status info lines while reading the data lines from the client. After this the key generation takes place and the server eventually does send an ERR or OK response. Status lines may be issued as a progress indicator.

5.6.6 List available keys

To list the keys in the internal database or using an external key provider, the command:

LISTKEYS *pattern*

is used. To allow multiple patterns (which are ORed during the search) quoting is required: Spaces are to be translated into "+" or into "%20"; in turn this requires that the usual escape quoting rules are done.

LISTSECRETKEYS *pattern*

Lists only the keys where a secret key is available.

The list commands are affected by the option

OPTION list-mode=*mode*

where mode may be:

- 0 Use default (which is usually the same as 1).
- 1 List only the internal keys.
- 2 List only the external keys.
- 3 List internal and external keys.

Note that options are valid for the entire session.

5.6.7 Export certificates

To export certificate from the internal key database the command:

EXPORT [--data [--armor] [--base64]] [--] *pattern*

is used. To allow multiple patterns (which are ORed) quoting is required: Spaces are to be translated into "+" or into "%20"; in turn this requires that the usual escape quoting rules are done.

If the '--data' option has not been given, the format of the output depends on what was set with the OUTPUT command. When using PEM encoding a few informational lines are prepended.

If the '--data' has been given, a target set via OUTPUT is ignored and the data is returned inline using standard D-lines. This avoids the need for an extra file descriptor. In this case the options '--armor' and '--base64' may be used in the same way as with the OUTPUT command.

5.6.8 Import certificates

To import certificates into the internal key database, the command

IMPORT [--re-import]

is used. The data is expected on the file descriptor set with the INPUT command. Certain checks are performed on the certificate. Note that the code will also handle PKCS#12 files and import private keys; a helper program is used for that.

With the option '--re-import' the input data is expected to be a linefeed separated list of fingerprints. The command will re-import the corresponding certificates; that is they are made permanent by removing their ephemeral flag.

5.6.9 Delete certificates

To delete a certificate the command

`DELKEYS pattern`

is used. To allow multiple patterns (which are ORed) quoting is required: Spaces are to be translated into "+" or into "%20"; in turn this requires that the usual escape quoting rules are done.

The certificates must be specified unambiguously otherwise an error is returned.

5.6.10 Retrieve an audit log

This command is used to retrieve an audit log.

`GETAUDITLOG [--data] [--html]`

If ‘--data’ is used, the audit log is send using D-lines instead of being sent to the file descriptor given by an `OUTPUT` command. If ‘--html’ is used, the output is formatted as an XHTML block. This is designed to be incorporated into a HTML document.

5.6.11 Return information about the process

This is a multipurpose function to return a variety of information.

`GETINFO what`

The value of *what* specifies the kind of information returned:

version Return the version of the program.

pid Return the process id of the process.

agent-check
 Return OK if the agent is running.

cmd_has_option *cmd opt*
 Return OK if the command *cmd* implements the option *opt*. The leading two dashes usually used with *opt* shall not be given.

offline Return OK if the connection is in offline mode. This may be either due to a `OPTION offline=1` or due to `gpgsm` being started with option ‘--disable-dirmngr’.

5.6.12 Session options

The standard Assuan option handler supports these options.

`OPTION name [=value]`

These *names* are recognized:

putenv Change the session’s environment to be passed via `gpg-agent` to `Pinentry`. *value* is a string of the form `<KEY>[=[<STRING>]]`. If only `<KEY>` is given the environment variable `<KEY>` is removed from the session environment, if `<KEY>=` is given that environment variable is set to the empty string, and if `<STRING>` is given it is set to that string.

display Set the session environment variable `DISPLAY` is set to *value*.

ttyname Set the session environment variable `GPG_TTY` is set to *value*.

- ttytype** Set the session environment variable `TERM` is set to *value*.
- lc-ctype** Set the session environment variable `LC_CTYPE` is set to *value*.
- lc-messages**
Set the session environment variable `LC_MESSAGES` is set to *value*.
- xauthority**
Set the session environment variable `XAUTHORITY` is set to *value*.
- pinentry-user-data**
Set the session environment variable `PINENTRY_USER_DATA` is set to *value*.
- include-certs**
This option overrides the command line option ‘`--include-certs`’. A *value* of -2 includes all certificates except for the root certificate, -1 includes all certificates, 0 does not include any certificates, 1 includes only the signers certificate and all other positive values include up to *value* certificates starting with the signer cert.
- list-mode**
See [\[gpgsm-cmd listkeys\]](#), page 113.
- list-to-output**
If *value* is true the output of the list commands (see [\[gpgsm-cmd listkeys\]](#), page 113) is written to the file descriptor set with the last `OUTPUT` command. If *value* is false the output is written via data lines; this is the default.
- with-validation**
If *value* is true for each listed certificate the validation status is printed. This may result in the download of a CRL or the user being asked about the trustworthiness of a root certificate. The default is given by a command line option (see [\[gpgsm-option --with-validation\]](#), page 103).
- with-secret**
If *value* is true certificates with a corresponding private key are marked by the list commands.
- validation-model**
This option overrides the command line option ‘`validation-model`’ for the session. (See [\[gpgsm-option --validation-model\]](#), page 102.)
- with-key-data**
This option globally enables the command line option ‘`--with-key-data`’. (See [\[gpgsm-option --with-key-data\]](#), page 103.)
- enable-audit-log**
If *value* is true data to write an audit log is gathered. (See [\[gpgsm-cmd getauditlog\]](#), page 115.)
- allow-pinentry-notify**
If this option is used notifications about the launch of a Pinentry are passed back to the client.

with-ephemeral-keys

If *value* is true ephemeral certificates are included in the output of the list commands.

no-encrypt-to

If this option is used all keys set by the command line option ‘--encrypt-to’ are ignored.

offline

If *value* is true or *value* is not given all network access is disabled for this session. This is the same as the command line option ‘--disable-dirmngr’.

6 Invoking the SCDAEMON

The `sddaemon` is a daemon to manage smartcards. It is usually invoked by `gpg-agent` and in general not used directly.

See [Option Index], page 197, for an index to `sddaemon`'s commands and options.

6.1 Commands

Commands are not distinguished from options except for the fact that only one command is allowed.

--version

Print the program version and licensing information. Note that you cannot abbreviate this command.

--help, -h

Print a usage message summarizing the most useful command-line options. Note that you cannot abbreviate this command.

--dump-options

Print a list of all available options and commands. Note that you cannot abbreviate this command.

--server Run in server mode and wait for commands on the `stdin`. The default mode is to create a socket and listen for commands there.

--multi-server

Run in server mode and wait for commands on the `stdin` as well as on an additional Unix Domain socket. The server command `GETINFO` may be used to get the name of that extra socket.

--daemon Run the program in the background. This option is required to prevent it from being accidentally running in the background.

6.2 Option Summary

--options *file*

Reads configuration from *file* instead of from the default per-user configuration file. The default configuration file is named '`sddaemon.conf`' and expected in the '`.gnupg`' directory directly below the home directory of the user.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to '`~/gnupg`'. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable `GNUPGHOME` or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named 'gpgconf.ct1' in the same directory as the tool 'gpgconf.exe'. The root of the installation is then that directory; or, if 'gpgconf.exe' has been installed directly below a directory named 'bin', its parent directory. You also need to make sure that the following directories exist and are writable: 'ROOT/home' for the GnuPG home and 'ROOT/var/cache/gnupg' for internal cache files.

-v

--verbose

Outputs additional information while running. You can increase the verbosity by giving several verbose commands to gpgsm, such as '-vv'.

--debug-level *level*

Select the debug level for investigating problems. *level* may be a numeric value or a keyword:

none	No debugging at all. A value of less than 1 may be used instead of the keyword.
basic	Some basic debug messages. A value between 1 and 2 may be used instead of the keyword.
advanced	More verbose debug messages. A value between 3 and 5 may be used instead of the keyword.
expert	Even more detailed messages. A value between 6 and 8 may be used instead of the keyword.
guru	All of the debug messages you can get. A value greater than 8 may be used instead of the keyword. The creation of hash tracing files is only enabled if the keyword is used.

How these messages are mapped to the actual debugging flags is not specified and may change with newer releases of this program. They are however carefully selected to best aid in debugging.

Note: All debugging options are subject to change and thus should not be used by any application program. As the name says, they are only used as helpers to debug problems.

--debug *flags*

This option is only useful for debugging and the behavior may change at any time without notice. FLAGS are bit encoded and may be given in usual C-Syntax. The currently defined bits are:

0 (1)	command I/O
1 (2)	values of big number integers
2 (4)	low level crypto operations
5 (32)	memory allocation
6 (64)	caching

- 7 (128) show memory statistics
 - 9 (512) write hashed data to files named `dbgmd-000*`
 - 10 (1024) trace Assuan protocol. See also option ‘`--debug-assuan-log-cats`’.
 - 11 (2048) trace APDU I/O to the card. This may reveal sensitive data.
 - 12 (4096) trace some card reader related function calls.
- `--debug-all`
Same as `--debug=0xffffffff`
- `--debug-wait n`
When running in server mode, wait *n* seconds before entering the actual processing loop and print the pid. This gives time to attach a debugger.
- `--debug-ccid-driver`
Enable debug output from the included CCID driver for smartcards. Using this option twice will also enable some tracing of the T=1 protocol. Note that this option may reveal sensitive data.
- `--debug-disable-ticker`
This option disables all ticker functions like checking for card insertions.
- `--debug-allow-core-dump`
For security reasons we won’t create a core dump when the process aborts. For debugging purposes it is sometimes better to allow core dump. This option enables it and also changes the working directory to ‘`/tmp`’ when running in ‘`--server`’ mode.
- `--debug-log-tid`
This option appends a thread ID to the PID in the log output.
- `--debug-assuan-log-cats cats`
Changes the active Libassuan logging categories to *cats*. The value for *cats* is an unsigned integer given in usual C-Syntax. A value of 0 switches to a default category. If this option is not used the categories are taken from the environment variable `ASSUAN_DEBUG`. Note that this option has only an effect if the Assuan debug flag has also been with the option ‘`--debug`’. For a list of categories see the Libassuan manual.
- `--no-detach`
Don’t detach the process from the console. This is mainly useful for debugging.
- `--listen-backlog n`
Set the size of the queue for pending connections. The default is 64. This option has an effect only if ‘`--multi-server`’ is also used.
- `--log-file file`
Append all logging output to *file*. This is very helpful in seeing what the agent actually does. Use ‘`socket://`’ to log to socket.
- `--pcsc-driver library`
Use *library* to access the smartcard reader. The current default is ‘`libpcsc-lite.so`’. Instead of using this option you might also want to install a symbolic link to the default file name (e.g. from ‘`libpcsc-lite.so.1`’).

--ctapi-driver *library*

Use *library* to access the smartcard reader. The current default is 'libtowitzoko.so'. Note that the use of this interface is deprecated; it may be removed in future releases.

--disable-ccid

Disable the integrated support for CCID compliant readers. This allows falling back to one of the other drivers even if the internal CCID driver can handle the reader. Note, that CCID support is only available if libusb was available at build time.

--reader-port *number_or_string*

This option may be used to specify the port of the card terminal. A value of 0 refers to the first serial device; add 32768 to access USB devices. The default is 32768 (first USB device). PC/SC or CCID readers might need a string here; run the program in verbose mode to get a list of available readers. The default is then the first reader found.

To get a list of available CCID readers you may use this command:

```
echo scd getinfo reader_list \
  | gpg-connect-agent --decode | awk '/^D/ {print $2}'
```

--card-timeout *n*

If *n* is not 0 and no client is actively using the card, the card will be powered down after *n* seconds. Powering down the card avoids a potential risk of damaging a card when used with certain cheap readers. This also allows applications that are not aware of Scdaemon to access the card. The disadvantage of using a card timeout is that accessing the card takes longer and that the user needs to enter the PIN again after the next power up.

Note that with the current version of Scdaemon the card is powered down immediately at the next timer tick for any value of *n* other than 0.

--enable-pinpad-varlen

Please specify this option when the card reader supports variable length input for pinpad (default is no). For known readers (listed in ccid-driver.c and apdu.c), this option is not needed. Note that if your card reader doesn't support variable length input but you want to use it, you need to specify your pinpad request on your card.

--disable-pinpad

Even if a card reader features a pinpad, do not try to use it.

--deny-admin

This option disables the use of admin class commands for card applications where this is supported. Currently we support it for the OpenPGP card. This option is useful to inhibit accidental access to admin class command which could ultimately lock the card through wrong PIN numbers. Note that GnuPG versions older than 2.0.11 featured an '--allow-admin' option which was required to use such admin commands. This option has no more effect today because the default is now to allow admin commands.

--disable-application *name*

This option disables the use of the card application named *name*. This is mainly useful for debugging or if a application with lower priority should be used by default.

All the long options may also be given in the configuration file after stripping off the two leading dashes.

6.3 Description of card applications

`scdaemon` supports the card applications as described below.

6.3.1 The OpenPGP card application “openpgp”

This application is currently only used by `gpg` but may in future also be useful with `gpgsm`. Version 1 and version 2 of the card is supported.

The specifications for these cards are available at

<http://g10code.com/docs/openpgp-card-1.0.pdf> and
<http://g10code.com/docs/openpgp-card-2.0.pdf>.

6.3.2 The Telesec NetKey card “nks”

This is the main application of the Telesec cards as available in Germany. It is a superset of the German DINSIG card. The card is used by `gpgsm`.

6.3.3 The DINSIG card application “dinsig”

This is an application as described in the German draft standard *DIN V 66291-1*. It is intended to be used by cards supporting the German signature law and its bylaws (SigG and SigV).

6.3.4 The PKCS#15 card application “p15”

This is common framework for smart card applications. It is used by `gpgsm`.

6.3.5 The Geldkarte card application “geldkarte”

This is a simple application to display information of a German Geldkarte. The Geldkarte is a small amount debit card application which comes with almost all German banking cards.

6.3.6 The SmartCard-HSM card application “sc-hsm”

This application adds read-only support for keys and certificates stored on a **SmartCard-HSM**.

To generate keys and store certificates you may use **OpenSC** or the tools from **OpenSCDP**.

The SmartCard-HSM cards requires a card reader that supports Extended Length APDUs.

6.3.7 The Undefined card application “undefined”

This is a stub application to allow the use of the APDU command even if no supported application is found on the card. This application is not used automatically but must be explicitly requested using the `SERIALNO` command.

6.4 Configuration files

There are a few configuration files to control certain aspects of **scdaemons**'s operation. Unless noted, they are expected in the current home directory (see [option `-homedir`], page 4).

`'scdaemon.conf'`

This is the standard configuration file read by **scdaemon** on startup. It may contain any valid long option; the leading two dashes may not be entered and the option may not be abbreviated. This default name may be changed on the command line (see [option `-options`], page 4).

`'scd-event'`

If this file is present and executable, it will be called on every card reader's status change. An example of this script is provided with the distribution

`'reader_n.status'`

This file is created by **scdaemon** to let other applications know about reader status changes. Its use is now deprecated in favor of `'scd-event'`.

6.5 Examples

```
$ scdaemon --server -v
```

6.6 Scdaemon's Assuan Protocol

The SC-Daemon should be started by the system to provide access to external tokens. Using Smartcards on a multi-user system does not make much sense except for system services, but in this case no regular user accounts are hosted on the machine.

A client connects to the SC-Daemon by connecting to the socket named `'/var/run/gnupg/scdaemon/socket'`, configuration information is read from `/etc/gnupg/scdaemon.conf`

Each connection acts as one session, SC-Daemon takes care of synchronizing access to a token between sessions.

6.6.1 Return the serial number

This command should be used to check for the presence of a card. It is special in that it can be used to reset the card. Most other commands will return an error when a card change has been detected and the use of this function is therefore required.

Background: We want to keep the client clear of handling card changes between operations; i.e. the client can assume that all operations are done on the same card unless he call this function.

```
SERIALNO
```

Return the serial number of the card using a status response like:

```
S SERIALNO D2760000000000000000000000000000
```

The serial number is the hex encoded value identified by the `0x5A` tag in the GDO file (FIX=0x2F02).

6.6.2 Read all useful information from the card

LEARN [--force]

Learn all useful information of the currently inserted card. When used without the '--force' option, the command might do an INQUIRE like this:

INQUIRE **KNOWNCARDP** <hexstring_with_serialNumber>

The client should just send an **END** if the processing should go on or a **CANCEL** to force the function to terminate with a cancel error message. The response of this command is a list of status lines formatted as this:

S **KEYPAIRINFO** *hexstring_with_keygrip hexstring_with_id*

If there is no certificate yet stored on the card a single "X" is returned in *hexstring_with_keygrip*.

6.6.3 Return a certificate

READCERT *hexified_certid|keyid*

This function is used to read a certificate identified by *hexified_certid* from the card. With OpenPGP cards the *keyid* **OpenPGP.3** may be used to read the certificate of version 2 cards.

6.6.4 Return a public key

READKEY *hexified_certid*

Return the public key for the given cert or key ID as an standard S-Expression.

6.6.5 Signing data with a Smartcard

To sign some data the caller should use the command

SETDATA *hexstring*

to tell **scdaemon** about the data to be signed. The data must be given in hex notation. The actual signing is done using the command

PKSIGN *keyid*

where *keyid* is the hexified ID of the key to be used. The key id may have been retrieved using the command **LEARN**. If another hash algorithm than SHA-1 is used, that algorithm may be given like:

PKSIGN --hash=*algoname* *keyid*

With *algoname* are one of **sha1**, **rmd160** or **md5**.

6.6.6 Decrypting data with a Smartcard

To decrypt some data the caller should use the command

SETDATA *hexstring*

to tell **scdaemon** about the data to be decrypted. The data must be given in hex notation. The actual decryption is then done using the command

PKDECRYPT *keyid*

where *keyid* is the hexified ID of the key to be used.

If the card is aware of the apdding format a status line with padding information is send before the plaintext data. The key for this status line is `PADDING` with the only defined value being 0 and meaning padding has been removed.

6.6.7 Read an attribute's value

TO BE WRITTEN.

6.6.8 Update an attribute's value

TO BE WRITTEN.

6.6.9 Write a key to a card

`WRITEKEY [--force] keyid`

This command is used to store a secret key on a smartcard. The allowed keyids depend on the currently selected smartcard application. The actual keydata is requested using the inquiry `KEYDATA` and need to be provided without any protection. With '`--force`' set an existing key under this *keyid* will get overwritten. The key data is expected to be the usual canonical encoded S-expression.

A PIN will be requested in most cases. This however depends on the actual card application.

6.6.10 Generate a new key on-card

TO BE WRITTEN.

6.6.11 Return random bytes generated on-card

TO BE WRITTEN.

6.6.12 Change PINs

`PASSWD [--reset] [--nullpin] chvno`

Change the PIN or reset the retry counter of the card holder verification vector number *chvno*. The option '`--nullpin`' is used to initialize the PIN of TCOS cards (6 byte NullPIN only).

6.6.13 Perform a VERIFY operation

`CHECKPIN idstr`

Perform a VERIFY operation without doing anything else. This may be used to initialize a the PIN cache earlier to long lasting operations. Its use is highly application dependent:

OpenPGP

Perform a simple verify operation for CHV1 and CHV2, so that further operations won't ask for CHV2 and it is possible to do a cheap check on the PIN: If there is something wrong with the PIN entry system, only the regular CHV will get blocked and not the dangerous CHV3. *idstr* is the usual card's serial number in hex notation; an optional fingerprint part will get ignored.

There is however a special mode if *idstr* is suffixed with the literal string `[CHV3]`: In this case the Admin PIN is checked if and only if the retry counter is still at 3.

6.6.14 Perform a RESTART operation

RESTART

Restart the current connection; this is a kind of warm reset. It deletes the context used by this connection but does not actually reset the card.

This is used by gpg-agent to reuse a primary pipe connection and may be used by clients to backup from a conflict in the serial command; i.e. to select another application.

6.6.15 Send a verbatim APDU to the card

APDU [--atr] [--more] [--exlen[=*n*]] [*hexstring*]

Send an APDU to the current reader. This command bypasses the high level functions and sends the data directly to the card. *hexstring* is expected to be a proper APDU. If *hexstring* is not given no commands are send to the card; However the command will implicitly check whether the card is ready for use.

Using the option `--atr` returns the ATR of the card as a status message before any data like this:

```
S CARD-ATR 3BFA1300FF813180450031C173C00100009000B1
```

Using the option `--more` handles the card status word `MORE_DATA` (61xx) and concatenate all responses to one block.

Using the option `--exlen` the returned APDU may use extended length up to *N* bytes. If *N* is not given a default value is used (currently 4096).

7 How to Specify a User Id

There are different ways to specify a user ID to GnuPG. Some of them are only valid for **gpg** others are only good for **gpgsm**. Here is the entire list of ways to specify a key:

- By key Id. This format is deduced from the length of the string and its content or **0x** prefix. The key Id of an X.509 certificate are the low 64 bits of its SHA-1 fingerprint. The use of key Ids is just a shortcut, for all automated processing the fingerprint should be used.

When using **gpg** an exclamation mark (!) may be appended to force using the specified primary or secondary key and not to try and calculate which primary or secondary key to use.

The last four lines of the example give the key ID in their long form as internally used by the OpenPGP protocol. You can see the long key ID using the option ‘**--with-colons**’.

```
234567C4
0F34E556E
01347A56A
0xAB123456

234AABBCC34567C4
0F323456784E56EAB
01AB3FED1347A5612
0x234AABBCC34567C4
```

- By fingerprint. This format is deduced from the length of the string and its content or the **0x** prefix. Note, that only the 20 byte version fingerprint is available with **gpgsm** (i.e. the SHA-1 hash of the certificate).

When using **gpg** an exclamation mark (!) may be appended to force using the specified primary or secondary key and not to try and calculate which primary or secondary key to use.

The best way to specify a key Id is by using the fingerprint. This avoids any ambiguities in case that there are duplicated key IDs.

```
1234343434343434C434343434343434
1234343434343434C3434343434343734349A3434
0E1234343434343434343434EAB34843434343434
0xE1234343434343434343434EAB34843434343434
```

gpgsm also accepts colons between each pair of hexadecimal digits because this is the de-facto standard on how to present X.509 fingerprints. **gpg** also allows the use of the space separated SHA-1 fingerprint as printed by the key listing commands.

- By exact match on OpenPGP user ID. This is denoted by a leading equal sign. It does not make sense for X.509 certificates.

```
=Heinrich Heine <heinrichh@uni-duesseldorf.de>
```

- By exact match on an email address. This is indicated by enclosing the email address in the usual way with left and right angles.

```
<heinrichh@uni-duesseldorf.de>
```

- By partial match on an email address. This is indicated by prefixing the search string with an @. This uses a substring search but considers only the mail address (i.e. inside the angle brackets).

```
@heinrichh
```

- By exact match on the subject's DN. This is indicated by a leading slash, directly followed by the RFC-2253 encoded DN of the subject. Note that you can't use the string printed by `gpgsm --list-keys` because that one has been reordered and modified for better readability; use `'--with-colons'` to print the raw (but standard escaped) RFC-2253 string.

```
/CN=Heinrich Heine,O=Poets,L=Paris,C=FR
```

- By exact match on the issuer's DN. This is indicated by a leading hash mark, directly followed by a slash and then directly followed by the RFC-2253 encoded DN of the issuer. This should return the Root cert of the issuer. See note above.

```
#/CN=Root Cert,O=Poets,L=Paris,C=FR
```

- By exact match on serial number and issuer's DN. This is indicated by a hash mark, followed by the hexadecimal representation of the serial number, then followed by a slash and the RFC-2253 encoded DN of the issuer. See note above.

```
#4F03/CN=Root Cert,O=Poets,L=Paris,C=FR
```

- By keygrip. This is indicated by an ampersand followed by the 40 hex digits of a keygrip. `gpgsm` prints the keygrip when using the command `'--dump-cert'`.

```
&D75F22C3F86E355877348498CDC92BD21010A480
```

- By substring match. This is the default mode but applications may want to explicitly indicate this by putting the asterisk in front. Match is not case sensitive.

```
Heine
*Heine
```

- . and + prefixes These prefixes are reserved for looking up mails anchored at the end and for a word search mode. They are not yet implemented and using them is undefined.

Please note that we have reused the hash mark identifier which was used in old GnuPG versions to indicate the so called local-id. It is not anymore used and there should be no conflict when used with X.509 stuff.

Using the RFC-2253 format of DNs has the drawback that it is not possible to map them back to the original encoding, however we don't have to do this because our key database stores this encoding as meta data.

8 Trust Values

Trust values are used to indicate ownertrust and validity of keys and user IDs. They are displayed with letters or strings:

-	
unknown	No ownertrust assigned / not yet calculated.
e	
expired	Trust calculation has failed; probably due to an expired key.
q	
undefined, undef	Not enough information for calculation.
n	
never	Never trust this key.
m	
marginal	Marginally trusted.
f	
full	Fully trusted.
u	
ultimate	Ultimately trusted.
r	
revoked	For validity only: the key or the user ID has been revoked.
?	
err	The program encountered an unknown trust value.

9 Helper Tools

GnuPG comes with a couple of smaller tools:

9.1 Read logs from a socket

Most of the main utilities are able to write their log files to a Unix Domain socket if configured that way. `watchgnupg` is a simple listener for such a socket. It ameliorates the output with a time stamp and makes sure that long lines are not interspersed with log output from other utilities. This tool is not available for Windows.

`watchgnupg` is commonly invoked as

```
watchgnupg --force $(gpgconf --list-dirs socketdir)/S.log
```

This starts it on the current terminal for listening on the standard logging socket (which is either `~/gnupg/S.log` or `/var/run/user/UID/gnupg/S.log`).

`watchgnupg` understands these options:

- `--force` Delete an already existing socket file.
- `--tcp n` Instead of reading from a local socket, listen for connects on TCP port *n*.
- `--time-only`
Do not print the date part of the timestamp.
- `--verbose`
Enable extra informational output.
- `--version`
Print version of the program and exit.
- `--help` Display a brief help page and exit.

Examples

```
$ watchgnupg --force --time-only $(gpgconf --list-dirs socketdir)/S.log
```

This waits for connections on the local socket (e.g. `/home/foo/.gnupg/S.log`) and shows all log entries. To make this work the option `'log-file'` needs to be used with all modules which logs are to be shown. The suggested entry for the configuration files is:

```
log-file socket://
```

If the default socket as given above and returned by `"echo $(gpgconf --list-dirs socketdir)/S.log"` is not desired an arbitrary socket name can be specified, for example `'socket:///home/foo/bar/mysocket'`. For debugging purposes it is also possible to do remote logging. Take care if you use this feature because the information is send in the clear over the network. Use this syntax in the conf files:

```
log-file tcp://192.168.1.1:4711
```

You may use any port and not just 4711 as shown above; only IP addresses are supported (v4 and v6) and no host names. You need to start `watchgnupg` with the `'tcp'` option. Note that under Windows the registry entry `HKCU\Software\GNU\GnuPG:DefaultLogFile` can be used to change the default log output from `stderr` to whatever is given by that entry. However the only useful entry is a TCP name for remote debugging.

9.2 Verify OpenPGP signatures

`gpgv2` is an OpenPGP signature verification tool.

This program is actually a stripped-down version of `gpg` which is only able to check signatures. It is somewhat smaller than the fully-blown `gpg` and uses a different (and simpler) way to check that the public keys used to make the signature are valid. There are no configuration files and only a few options are implemented.

`gpgv2` assumes that all keys in the keyring are trustworthy. That does also mean that it does not check for expired or revoked keys.

If no `--keyring` option is given, `gpgv` looks for a “default” keyring named ‘`trustedkeys.kbx`’ (preferred) or ‘`trustedkeys.gpg`’ in the home directory of GnuPG, either the default home directory or the one set by the `--homedir` option or the `GNUPGHOME` environment variable. If any `--keyring` option is used, `gpgv` will not look for the default keyring. The `--keyring` option may be used multiple times and all specified keyrings will be used together.

`gpgv2` recognizes these options:

- `--verbose`
- `-v` Gives more information during processing. If used twice, the input data is listed in detail.
- `--quiet`
- `-q` Try to be as quiet as possible.
- `--keyring file`
Add *file* to the list of keyrings. If *file* begins with a tilde and a slash, these are replaced by the HOME directory. If the filename does not contain a slash, it is assumed to be in the home-directory (“`~/gnupg`” if `--homedir` is not used).
- `--output file`
- `-o file` Write output to *file*; to write to stdout use `-`. This option can be used to get the signed text from a cleartext or binary signature; it also works for detached signatures, but in that case this option is in general not useful. Note that an existing file will be overwritten.
- `--status-fd n`
Write special status strings to the file descriptor *n*. See the file DETAILS in the documentation for a listing of them.
- `--logger-fd n`
Write log output to file descriptor *n* and not to stderr.
- `--log-file file`
Same as ‘`--logger-fd`’, except the logger data is written to file *file*. Use ‘`socket://`’ to log to socket.
- `--ignore-time-conflict`
GnuPG normally checks that the timestamps associated with keys and signatures have plausible values. However, sometimes a signature seems to be older than the key due to clock problems. This option turns these checks into warnings.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to '`~/.gnupg`'. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable `GNUPGHOME` or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named '`gpgconfctl`' in the same directory as the tool '`gpgconf.exe`'. The root of the installation is then that directory; or, if '`gpgconf.exe`' has been installed directly below a directory named '`bin`', its parent directory. You also need to make sure that the following directories exist and are writable: '`ROOT/home`' for the GnuPG home and '`ROOT/var/cache/gnupg`' for internal cache files.

--weak-digest *name*

Treat the specified digest algorithm as weak. Signatures made over weak digests algorithms are normally rejected. This option can be supplied multiple times if multiple algorithms should be considered weak. MD5 is always considered weak, and does not need to be listed explicitly.

--enable-special-filenames

This option enables a mode in which filenames of the form '`-%n`', where *n* is a non-negative decimal number, refer to the file descriptor *n* and not to a file with that name.

The program returns 0 if everything is fine, 1 if at least one signature was bad, and other error codes for fatal errors.

9.2.1 Examples

`gpgv2pgpfile`

`gpgv2sigfile [datafile]`

Verify the signature of the file. The second form is used for detached signatures, where `sigfile` is the detached signature (either ASCII-armored or binary) and `datafile` contains the signed data; if `datafile` is "-" the signed data is expected on `stdin`; if `datafile` is not given the name of the file holding the signed data is constructed by cutting off the extension (`".asc"`, `".sig"` or `".sign"`) from `sigfile`.

9.2.2 Environment

HOME Used to locate the default home directory.

GNUPGHOME

If set directory used instead of `"~/.gnupg"`.

9.2.3 FILES

`~/gnupg/trustedkeys.gpg`

The default keyring with the allowed keys.

`gpg(1)`

9.3 Create .gnupg home directories

If GnuPG is installed on a system with existing user accounts, it is sometimes required to populate the GnuPG home directory with existing files. Especially a `trustlist.txt` and a keybox with some initial certificates are often desired. This script helps to do this by copying all files from `/etc/skel/.gnupg` to the home directories of the accounts given on the command line. It takes care not to overwrite existing GnuPG home directories.

`addgnupghome` is invoked by root as:

```
addgnupghome account1 account2 ... accountn
```

9.4 Modify .gnupg home directories

The `gpgconf` is a utility to automatically and reasonably safely query and modify configuration files in the `.gnupg` home directory. It is designed not to be invoked manually by the user, but automatically by graphical user interfaces (GUI).¹

`gpgconf` provides access to the configuration of one or more components of the GnuPG system. These components correspond more or less to the programs that exist in the GnuPG framework, like GPG, GPGSM, DirMngr, etc. But this is not a strict one-to-one relationship. Not all configuration options are available through `gpgconf`. `gpgconf` provides a generic and abstract method to access the most important configuration options that can feasibly be controlled via such a mechanism.

`gpgconf` can be used to gather and change the options available in each component, and can also provide their default values. `gpgconf` will give detailed type information that can be used to restrict the user's input without making an attempt to commit the changes.

`gpgconf` provides the backend of a configuration editor. The configuration editor would usually be a graphical user interface program that displays the current options, their default values, and allows the user to make changes to the options. These changes can then be made active with `gpgconf` again. Such a program that uses `gpgconf` in this way will be called GUI throughout this section.

9.4.1 Invoking gpgconf

One of the following commands must be given:

`--list-components`

List all components. This is the default command used if none is specified.

`--check-programs`

List all available backend programs and test whether they are runnable.

¹ Please note that currently no locking is done, so concurrent access should be avoided. There are some precautions to avoid corruption with concurrent usage, but results may be inconsistent and some changes may get lost. The stateless design makes it difficult to provide more guarantees.

- `--list-options component`
List all options of the component *component*.
- `--change-options component`
Change the options of the component *component*.
- `--check-options component`
Check the options for the component *component*.
- `--apply-profile file`
Apply the configuration settings listed in *file* to the configuration files. If *file* has no suffix and no slashes the command first tries to read a file with the suffix `.prf` from the data directory (`gpgconf --list-dirs datadir`) before it reads the file verbatim. A profile is divided into sections using the bracketed component name. Each section then lists the option which shall go into the respective configuration file.
- `--apply-defaults`
Update all configuration files with values taken from the global configuration file (usually `/etc/gnupg/gpgconf.conf`).
- `--list-dirs [names]`
Lists the directories used by `gpgconf`. One directory is listed per line, and each line consists of a colon-separated list where the first field names the directory type (for example `sysconfdir`) and the second field contains the percent-escaped directory. Although they are not directories, the socket file names used by `gpg-agent` and `dirmngr` are printed as well. Note that the socket file names and the `homedir` lines are the default names and they may be overridden by command line switches. If *names* are given only the directories or file names specified by the list names are printed without any escaping.
- `--list-config [filename]`
List the global configuration file in a colon separated format. If *filename* is given, check that file instead.
- `--check-config [filename]`
Run a syntax check on the global configuration file. If *filename* is given, check that file instead.
- `--query-swdb package_name [version_string]`
Returns the current version for *package_name* and if *version_string* is given also an indicator on whether an update is available. The actual file with the software version is automatically downloaded and checked by `dirmngr`. `dirmngr` uses a thresholds to avoid download the file too often and it does this by default only if it can be done via Tor. To force an update of that file this command can be used:

`gpg-connect-agent --dirmngr 'loadswdb --force' /bye`
- `--reload [component]`
Reload all or the given component. This is basically the same as sending a `SIGHUP` to the component. Components which don't support reloading are

ignored. Without *component* or by using "all" for *component* all components which are daemons are reloaded.

--launch [*component*]

If the *component* is not already running, start it. *component* must be a daemon. This is in general not required because the system starts these daemons as needed. However, external software making direct use of *gpg-agent* or *dirmngr* may use this command to ensure that they are started. Using "all" for *component* launches all components which are daemons.

--kill [*component*]

Kill the given component that runs as a daemon, including *gpg-agent*, *dirmngr*, and *scdaemon*. A *component* which does not run as a daemon will be ignored. Using "all" for *component* kills all components running as daemons. Note that as of now reload and kill have the same effect for *scdaemon*.

--create-socketdir

Create a directory for sockets below /run/user or /var/run/user. This is command is only required if a non default home directory is used and the /run based sockets shall be used. For the default home directory GnUPG creates a directory on the fly.

--remove-socketdir

Remove a directory created with command '**--create-socketdir**'.

The following options may be used:

-o *file*

--output *file*

Write output to *file*. Default is to write to stdout.

-v

--verbose

Outputs additional information while running. Specifically, this extends numerical field values by human-readable descriptions.

-q

--quiet Try to be as quiet as possible.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to '~/.gnupg'. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable *GNUPGHOME* or (on Windows systems) by means of the Registry entry *HKCU\Software\GNU\GnuPG:HomeDir*.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named '*gpgconf.ct1*' in the same directory as the tool '*gpgconf.exe*'. The root of the installation is then that directory; or, if '*gpgconf.exe*' has

been installed directly below a directory named ‘bin’, its parent directory. You also need to make sure that the following directories exist and are writable: ‘ROOT/home’ for the GnuPG home and ‘ROOT/var/cache/gnupg’ for internal cache files.

-n

--dry-run

Do not actually change anything. This is currently only implemented for **--change-options** and can be used for testing purposes.

-r

--runtime

Only used together with **--change-options**. If one of the modified options can be changed in a running daemon process, signal the running daemon to ask it to reparse its configuration file after changing.

This means that the changes will take effect at run-time, as far as this is possible. Otherwise, they will take effect at the next start of the respective backend programs.

--status-fd n

Write special status strings to the file descriptor *n*. This program returns the status messages SUCCESS or FAILURE which are helpful when the caller uses a double fork approach and can’t easily get the return code of the process.

9.4.2 Format conventions

Some lines in the output of **gpgconf** contain a list of colon-separated fields. The following conventions apply:

- The GUI program is required to strip off trailing newline and/or carriage return characters from the output.
- **gpgconf** will never leave out fields. If a certain version provides a certain field, this field will always be present in all **gpgconf** versions from that time on.
- Future versions of **gpgconf** might append fields to the list. New fields will always be separated from the previously last field by a colon separator. The GUI should be prepared to parse the last field it knows about up until a colon or end of line.
- Not all fields are defined under all conditions. You are required to ignore the content of undefined fields.

There are several standard types for the content of a field:

verbatim Some fields contain strings that are not escaped in any way. Such fields are described to be used *verbatim*. These fields will never contain a colon character (for obvious reasons). No de-escaping or other formatting is required to use the field content. This is for easy parsing of the output, when it is known that the content can never contain any special characters.

percent-escaped

Some fields contain strings that are described to be *percent-escaped*. Such strings need to be de-escaped before their content can be presented to the user. A percent-escaped string is de-escaped by replacing all occurrences of **%XY** by the byte that has the hexadecimal value XY. X and Y are from the set 0-9a-f.

- localized Some fields contain strings that are described to be *localized*. Such strings are translated to the active language and formatted in the active character set.
- unsigned number Some fields contain an *unsigned number*. This number will always fit into a 32-bit unsigned integer variable. The number may be followed by a space, followed by a human readable description of that value (if the verbose option is used). You should ignore everything in the field that follows the number.
- signed number Some fields contain a *signed number*. This number will always fit into a 32-bit signed integer variable. The number may be followed by a space, followed by a human readable description of that value (if the verbose option is used). You should ignore everything in the field that follows the number.
- boolean value Some fields contain a *boolean value*. This is a number with either the value 0 or 1. The number may be followed by a space, followed by a human readable description of that value (if the verbose option is used). You should ignore everything in the field that follows the number; checking just the first character is sufficient in this case.
- option Some fields contain an *option* argument. The format of an option argument depends on the type of the option and on some flags:
- no argument The simplest case is that the option does not take an argument at all (*type* 0). Then the option argument is an unsigned number that specifies how often the option occurs. If the `list` flag is not set, then the only valid number is 1. Options that do not take an argument never have the `default` or `optional arg` flag set.
 - number If the option takes a number argument (*alt-type* is 2 or 3), and it can only occur once (`list` flag is not set), then the option argument is either empty (only allowed if the argument is optional), or it is a number. A number is a string that begins with an optional minus character, followed by one or more digits. The number must fit into an integer variable (unsigned or signed, depending on *alt-type*).
 - number list If the option takes a number argument and it can occur more than once, then the option argument is either empty, or it is a comma-separated list of numbers as described above.
 - string If the option takes a string argument (*alt-type* is 1), and it can only occur once (`list` flag is not set) then the option argument is either empty (only allowed if the argument is optional), or it starts with a double quote character (") followed by a percent-escaped string that is the argument value. Note that there is only a leading double quote character, no trailing one. The double quote character is only needed to be able to differentiate between no value and the empty string as value.

string list If the option takes a string argument and it can occur more than once, then the option argument is either empty, or it is a comma-separated list of string arguments as described above.

The active language and character set are currently determined from the locale environment of the `gpgconf` program.

9.4.3 Listing components

The command `--list-components` will list all components that can be configured with `gpgconf`. Usually, one component will correspond to one GnuPG-related program and contain the options of that program's configuration file that can be modified using `gpgconf`. However, this is not necessarily the case. A component might also be a group of selected options from several programs, or contain entirely virtual options that have a special effect rather than changing exactly one option in one configuration file.

A component is a set of configuration options that semantically belong together. Furthermore, several changes to a component can be made in an atomic way with a single operation. The GUI could for example provide a menu with one entry for each component, or a window with one tabulator sheet per component.

The command `--list-components` lists all available components, one per line. The format of each line is:

name:description:pgmname:

name This field contains a name tag of the component. The name tag is used to specify the component in all communication with `gpgconf`. The name tag is to be used *verbatim*. It is thus not in any escaped format.

description The *string* in this field contains a human-readable description of the component. It can be displayed to the user of the GUI for informational purposes. It is *percent-escaped* and *localized*.

pgmname The *string* in this field contains the absolute name of the program's file. It can be used to unambiguously invoke that program. It is *percent-escaped*.

Example:

```
$ gpgconf --list-components
gpg:GPG for OpenPGP:/usr/local/bin/gpg2:
gpg-agent:GPG Agent:/usr/local/bin/gpg-agent:
scdaemon:Smartcard Daemon:/usr/local/bin/scdaemon:
gpgsm:GPG for S/MIME:/usr/local/bin/gpgsm:
dirmngr:Directory Manager:/usr/local/bin/dirmngr:
```

9.4.4 Checking programs

The command `--check-programs` is similar to `--list-components` but works on backend programs and not on components. It runs each program to test whether it is installed and runnable. This also includes a syntax check of all config file options of the program.

The command `--check-programs` lists all available programs, one per line. The format of each line is:

name:description:pgmname:avail:okay:cfgfile:line:error:

<i>name</i>	This field contains a name tag of the program which is identical to the name of the component. The name tag is to be used <i>verbatim</i> . It is thus not in any escaped format. This field may be empty to indicate a continuation of error descriptions for the last name. The description and pgmname fields are then also empty.
<i>description</i>	The <i>string</i> in this field contains a human-readable description of the component. It can be displayed to the user of the GUI for informational purposes. It is <i>percent-escaped</i> and <i>localized</i> .
<i>pgmname</i>	The <i>string</i> in this field contains the absolute name of the program's file. It can be used to unambiguously invoke that program. It is <i>percent-escaped</i> .
<i>avail</i>	The <i>boolean value</i> in this field indicates whether the program is installed and runnable.
<i>okay</i>	The <i>boolean value</i> in this field indicates whether the program's config file is syntactically okay.
<i>cfgfile</i>	If an error occurred in the configuration file (as indicated by a false value in the field <i>okay</i>), this field has the name of the failing configuration file. It is <i>percent-escaped</i> .
<i>line</i>	If an error occurred in the configuration file, this field has the line number of the failing statement in the configuration file. It is an <i>unsigned number</i> .
<i>error</i>	If an error occurred in the configuration file, this field has the error text of the failing statement in the configuration file. It is <i>percent-escaped</i> and <i>localized</i> .

In the following example the `dirmngr` is not runnable and the configuration file of `scdaemon` is not okay.

```
$ gpgconf --check-programs
gpg:GPG for OpenPGP:/usr/local/bin/gpg2:1:1:
gpg-agent:GPG Agent:/usr/local/bin/gpg-agent:1:1:
scdaemon:Smartcard Daemon:/usr/local/bin/scdaemon:1:0:
gpgsm:GPG for S/MIME:/usr/local/bin/gpgsm:1:1:
dirmngr:Directory Manager:/usr/local/bin/dirmngr:0:0:
```

The command `--check-options component` will verify the configuration file in the same manner as `--check-programs`, but only for the component *component*.

9.4.5 Listing options

Every component contains one or more options. Options may be gathered into option groups to allow the GUI to give visual hints to the user about which options are related.

The command `--list-options component` lists all options (and the groups they belong to) in the component *component*, one per line. *component* must be the string in the field *name* in the output of the `--list-components` command.

There is one line for each option and each group. First come all options that are not in any group. Then comes a line describing a group. Then come all options that belong into each group. Then comes the next group and so on. There does not need to be any group (and in this case the output will stop after the last non-grouped option).

The format of each line is:

`name:flags:level:description:type:alt-type:argname:default:argdef:value`■

name This field contains a name tag for the group or option. The name tag is used to specify the group or option in all communication with `gpgconf`. The name tag is to be used *verbatim*. It is thus not in any escaped format.

flags The flags field contains an *unsigned number*. Its value is the OR-wise combination of the following flag values:

group (1) If this flag is set, this is a line describing a group and not an option.

The following flag values are only defined for options (that is, if the **group** flag is not used).

optional arg (2)

If this flag is set, the argument is optional. This is never set for *type 0* (none) options.

list (4) If this flag is set, the option can be given multiple times.

runtime (8)

If this flag is set, the option can be changed at runtime.

default (16)

If this flag is set, a default value is available.

default desc (32)

If this flag is set, a (runtime) default is available. This and the **default** flag are mutually exclusive.

no arg desc (64)

If this flag is set, and the **optional arg** flag is set, then the option has a special meaning if no argument is given.

no change (128)

If this flag is set, `gpgconf` ignores requests to change the value. GUI frontends should grey out this option. Note, that manual changes of the configuration files are still possible.

level This field is defined for options and for groups. It contains an *unsigned number* that specifies the expert level under which this group or option should be displayed. The following expert levels are defined for options (they have analogous meaning for groups):

basic (0) This option should always be offered to the user.

advanced (1)

This option may be offered to advanced users.

expert (2)

This option should only be offered to expert users.

invisible (3)

This option should normally never be displayed, not even to expert users.

internal (4)

This option is for internal use only. Ignore it.

The level of a group will always be the lowest level of all options it contains.

description

This field is defined for options and groups. The *string* in this field contains a human-readable description of the option or group. It can be displayed to the user of the GUI for informational purposes. It is *percent-escaped* and *localized*.

type

This field is only defined for options. It contains an *unsigned number* that specifies the type of the option's argument, if any. The following types are defined:

Basic types:

none (0) No argument allowed.

string (1)
An *unformatted string*.

int32 (2) A *signed number*.

uint32 (3)
An *unsigned number*.

Complex types:

pathname (32)
A *string* that describes the pathname of a file. The file does not necessarily need to exist.

ldap server (33)
A *string* that describes an LDAP server in the format:
hostname:port:username:password:base_dn

key fingerprint (34)
A *string* with a 40 digit fingerprint specifying a certificate.

pub key (35)
A *string* that describes a certificate by user ID, key ID or fingerprint.

sec key (36)
A *string* that describes a certificate with a key by user ID, key ID or fingerprint.

alias list (37)
A *string* that describes an alias list, like the one used with gpg's group option. The list consists of a key, an equal sign and space separated values.

More types will be added in the future. Please see the *alt-type* field for information on how to cope with unknown types.

<i>alt-type</i>	This field is identical to <i>type</i> , except that only the types 0 to 31 are allowed. The GUI is expected to present the user the option in the format specified by <i>type</i> . But if the argument type <i>type</i> is not supported by the GUI, it can still display the option in the more generic basic type <i>alt-type</i> . The GUI must support all the defined basic types to be able to display all options. More basic types may be added in future versions. If the GUI encounters a basic type it doesn't support, it should report an error and abort the operation.
<i>argname</i>	This field is only defined for options with an argument type <i>type</i> that is not 0. In this case it may contain a <i>percent-escaped</i> and <i>localized string</i> that gives a short name for the argument. The field may also be empty, though, in which case a short name is not known.
<i>default</i>	This field is defined only for options for which the default or default desc flag is set. If the default flag is set, its format is that of an <i>option argument</i> (see Section 9.4.2 [Format conventions] , page 141, for details). If the default value is empty, then no default is known. Otherwise, the value specifies the default value for this option. If the default desc flag is set, the field is either empty or contains a description of the effect if the option is not given.
<i>argdef</i>	This field is defined only for options for which the optional arg flag is set. If the no arg desc flag is not set, its format is that of an <i>option argument</i> (see Section 9.4.2 [Format conventions] , page 141, for details). If the default value is empty, then no default is known. Otherwise, the value specifies the default argument for this option. If the no arg desc flag is set, the field is either empty or contains a description of the effect of this option if no argument is given.
<i>value</i>	This field is defined only for options. Its format is that of an <i>option argument</i> . If it is empty, then the option is not explicitly set in the current configuration, and the default applies (if any). Otherwise, it contains the current value of the option. Note that this field is also meaningful if the option itself does not take a real argument (in this case, it contains the number of times the option appears).

9.4.6 Changing options

The command **--change-options** *component* will attempt to change the options of the component *component* to the specified values. *component* must be the string in the field *name* in the output of the **--list-components** command. You have to provide the options that shall be changed in the following format on standard input:

```
name:flags:new-value
```

<i>name</i>	This is the name of the option to change. <i>name</i> must be the string in the field <i>name</i> in the output of the --list-options command.
<i>flags</i>	The flags field contains an <i>unsigned number</i> . Its value is the OR-wise combination of the following flag values:

default (16)

If this flag is set, the option is deleted and the default value is used instead (if applicable).

new-value The new value for the option. This field is only defined if the **default** flag is not set. The format is that of an *option argument*. If it is empty (or the field is omitted), the default argument is used (only allowed if the argument is optional for this option). Otherwise, the option will be set to the specified value.

The output of the command is the same as that of **--check-options** for the modified configuration file.

Examples:

To set the force option, which is of basic type **none** (0):

```
$ echo 'force:0:1' | gpgconf --change-options dirmngr
```

To delete the force option:

```
$ echo 'force:16:' | gpgconf --change-options dirmngr
```

The **--runtime** option can influence when the changes take effect.

9.4.7 Listing global options

Sometimes it is useful for applications to look at the global options file '**gpgconf.conf**'. The colon separated listing format is record oriented and uses the first field to identify the record type:

k This describes a key record to start the definition of a new ruleset for a user/group. The format of a key record is:

k:user:group:

user This is the user field of the key. It is percent escaped. See the definition of the gpgconf.conf format for details.

group This is the group field of the key. It is percent escaped.

r This describes a rule record. All rule records up to the next key record make up a rule set for that key. The format of a rule record is:

r:::component:option:flag:value:

component

This is the component part of a rule. It is a plain string.

option This is the option part of a rule. It is a plain string.

flag This is the flags part of a rule. There may be only one flag per rule but by using the same component and option, several flags may be assigned to an option. It is a plain string.

value This is the optional value for the option. It is a percent escaped string with a single quotation mark to indicate a string. The quotation mark is only required to distinguish between no value specified and an empty string.

Unknown record types should be ignored. Note that there is intentionally no feature to change the global option file through **gpgconf**.

9.4.8 Get and compare software versions.

The GnuPG Project operates a server to query the current versions of software packages related to GnuPG. `gpgconf` can be used to access this online database. To allow for offline operations, this feature works by having `dirmngr` download a file from <https://versions.gnupg.org>, checking the signature of that file and storing the file in the GnuPG home directory. If `gpgconf` is used and `dirmngr` is running, it may ask `dirmngr` to refresh that file before itself uses the file.

The command ‘`--query-swdb`’ returns information for the given package in a colon delimited format:

<i>name</i>	This is the name of the package as requested. Note that "gnupg" is a special name which is replaced by the actual package implementing this version of GnuPG. For this name it is also not required to specify a version because <code>gpgconf</code> takes its own version in this case.										
<i>iversion</i>	The currently installed version or an empty string. The value is taken from the command line argument but may be provided by <code>gpg</code> if not given.										
<i>status</i>	The status of the software package according to this table: <table> <tr> <td>-</td><td>No information available. This is either because no current version has been specified or due to an error.</td></tr> <tr> <td>?</td><td>The given name is not known in the online database.</td></tr> <tr> <td>u</td><td>An update of the software is available.</td></tr> <tr> <td>c</td><td>The installed version of the software is current.</td></tr> <tr> <td>n</td><td>The installed version is already newer than the released version.</td></tr> </table>	-	No information available. This is either because no current version has been specified or due to an error.	?	The given name is not known in the online database.	u	An update of the software is available.	c	The installed version of the software is current.	n	The installed version is already newer than the released version.
-	No information available. This is either because no current version has been specified or due to an error.										
?	The given name is not known in the online database.										
u	An update of the software is available.										
c	The installed version of the software is current.										
n	The installed version is already newer than the released version.										
<i>urgency</i>	If the value (the empty string should be considered as zero) is greater than zero an important update is available.										
<i>error</i>	This returns an <code>gpg-error</code> error code to distinguish between various failure modes.										
<i>filedate</i>	This gives the date of the file with the version numbers in standard ISO format (<code>yyyymmddThhmmss</code>). The date has been extracted by <code>dirmngr</code> from the signature of the file.										
<i>verified</i>	This gives the date in ISO format the file was downloaded. This value can be used to evaluate the freshness of the information.										
<i>version</i>	This returns the version string for the requested software from the file.										
<i>reldate</i>	This returns the release date in ISO format.										
<i>size</i>	This returns the size of the package as decimal number of bytes.										
<i>hash</i>	This returns a hexified SHA-2 hash of the package.										

More fields may be added in future to the output.

9.4.9 Files used by gpgconf

`‘/etc/gnupg/gpgconf.conf’`

If this file exists, it is processed as a global configuration file. A commented example can be found in the `‘examples’` directory of the distribution.

`‘GNUPGHOME/swdb.lst’`

A file with current software versions. `dirmngr` creates this file on demand from an online resource.

9.5 Run gpgconf for all users

This script is a wrapper around `gpgconf` to run it with the command `--apply-defaults` for all real users with an existing GnuPG home directory. Admins might want to use this script to update the GnuPG configuration files for all users after `‘/etc/gnupg/gpgconf.conf’` has been changed. This allows enforcing certain policies for all users. Note, that this is not a bulletproof way to force a user to use certain options. A user may always directly edit the configuration files and bypass `gpgconf`.

`applygnupgdefaults` is invoked by root as:

```
applygnupgdefaults
```

9.6 Put a passphrase into the cache

The `gpg-preset-passphrase` is a utility to seed the internal cache of a running `gpg-agent` with passphrases. It is mainly useful for unattended machines, where the usual `pinentry` tool may not be used and the passphrases for the to be used keys are given at machine startup.

This program works with GnuPG 2 and later. GnuPG 1.x is not supported.

Passphrases set with this utility don’t expire unless the `‘--forget’` option is used to explicitly clear them from the cache — or `gpg-agent` is either restarted or reloaded (by sending a SIGHUP to it). Note that the maximum cache time as set with `‘--max-cache-ttl’` is still honored. It is necessary to allow this passphrase presetting by starting `gpg-agent` with the `‘--allow-preset-passphrase’`.

9.6.1 List of all commands and options

`gpg-preset-passphrase` is invoked this way:

```
gpg-preset-passphrase [options] [command] cacheid
```

`cacheid` is either a 40 character keygrip of hexadecimal characters identifying the key for which the passphrase should be set or cleared. The keygrip is listed along with the key when running the command: `gpgsm --with-keygrip --list-secret-keys`. Alternatively an arbitrary string may be used to identify a passphrase; it is suggested that such a string is prefixed with the name of the application (e.g `foo:12346`). Scripts should always use the option `‘--with-colons’`, which provides the keygrip in a `"grp"` line (cf. `‘doc/DETAILS’`)/

One of the following command options must be given:

`--preset` Preset a passphrase. This is what you usually will use. `gpg-preset-passphrase` will then read the passphrase from `stdin`.

--forget Flush the passphrase for the given cache ID from the cache.

The following additional options may be used:

-v

--verbose

Output additional information while running.

-P *string*

--passphrase *string*

Instead of reading the passphrase from **stdin**, use the supplied *string* as passphrase. Note that this makes the passphrase visible for other users.

9.7 Communicate with a running agent

The **gpg-connect-agent** is a utility to communicate with a running **gpg-agent**. It is useful to check out the commands **gpg-agent** provides using the Assuan interface. It might also be useful for scripting simple applications. Input is expected at **stdin** and output gets printed to **stdout**.

It is very similar to running **gpg-agent** in server mode; but here we connect to a running instance.

9.7.1 List of all options

gpg-connect-agent is invoked this way:

```
gpg-connect-agent [options] [commands]
```

The following options may be used:

-v

--verbose

Output additional information while running.

-q

--quiet Try to be as quiet as possible.

--homedir *dir*

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to `~/gnupg`. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable **GNUPGHOME** or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named `gpgconf.ct1` in the same directory as the tool `gpgconf.exe`. The root of the installation is then that directory; or, if `gpgconf.exe` has been installed directly below a directory named `bin`, its parent directory. You also need to make sure that the following directories exist and are writable: `ROOT/home` for the GnuPG home and `ROOT/var/cache/gnupg` for internal cache files.

- agent-program *file***
Specify the agent program to be started if none is running. The default value is determined by running `gpgconf` with the option '`--list-dirs`'. Note that the pipe symbol (`|`) is used for a regression test suite hack and may thus not be used in the file name.
- dirmngr-program *file***
Specify the directory manager (keyserver client) program to be started if none is running. This has only an effect if used together with the option '`--dirmngr`'.
- dirmngr**
Connect to a running directory manager (keyserver client) instead of to the `gpg-agent`. If a `dirmngr` is not running, start it.
- S**
- raw-socket *name***
Connect to socket *name* assuming this is an Assuan style server. Do not run any special initializations or environment checks. This may be used to directly connect to any Assuan style socket server.
- E**
- exec** Take the rest of the command line as a program and its arguments and execute it as an Assuan server. Here is how you would run `gpgsm`:
- `gpg-connect-agent --exec gpgsm --server`
- Note that you may not use options on the command line in this case.
- no-ext-connect**
When using '`-S`' or '`--exec`', `gpg-connect-agent` connects to the Assuan server in extended mode to allow descriptor passing. This option makes it use the old mode.
- no-autostart**
Do not start the `gpg-agent` or the `dirmngr` if it has not yet been started.
- r *file***
- run *file***
Run the commands from *file* at startup and then continue with the regular input method. Note, that commands given on the command line are executed after this file.
- s**
- subst** Run the command `/subst` at startup.
- hex** Print data lines in a hex format and the ASCII representation of non-control characters.
- decode** Decode data lines. That is to remove percent escapes but make sure that a new line always starts with a `D` and a space.

9.7.2 Control commands

While reading Assuan commands, `gpg-agent` also allows a few special commands to control its operation. These control commands all start with a slash (`/`).

`/echo args`

Just print *args*.

`/let name value`

Set the variable *name* to *value*. Variables are only substituted on the input if the `/subst` has been used. Variables are referenced by prefixing the name with a dollar sign and optionally include the name in curly braces. The rules for a valid name are identically to those of the standard bourne shell. This is not yet enforced but may be in the future. When used with curly braces no leading or trailing white space is allowed.

If a variable is not found, it is searched in the environment and if found copied to the table of variables.

Variable functions are available: The name of the function must be followed by at least one space and the at least one argument. The following functions are available:

get Return a value described by the argument. Available arguments are:

cwd The current working directory.

homedir The gnupg homedir.

sysconfdir GnuPG's system configuration directory.

bindir GnuPG's binary directory.

libdir GnuPG's library directory.

libexecdir GnuPG's library directory for executable files.

datadir GnuPG's data directory.

serverpid The PID of the current server. Command `/serverpid` must have been given to return a useful value.

unescape args

Remove C-style escapes from *args*. Note that `\0` and `\x00` terminate the returned string implicitly. The string to be converted are the entire arguments right behind the delimiting space of the function name.

unpercent args

unpercent+ args

Remove percent style escaping from *args*. Note that `%00` terminates the string implicitly. The string to be converted are the entire arguments right behind the delimiting space of the function name. **unpercent+** also maps plus signs to a spaces.

`percent args`
`percent+ args`

Escape the *args* using percent style escaping. Tabs, formfeeds, linefeeds, carriage returns and colons are escaped. `percent+` also maps spaces to plus signs.

`errcode arg`
`errsource arg`
`errstring arg`

Assume *arg* is an integer and evaluate it using `strtol`. Return the gpg-error error code, error source or a formatted string with the error code and error source.

`+`

`-`

`*`

`/`

`%`

Evaluate all arguments as long integers using `strtol` and apply this operator. A division by zero yields an empty string.

`!`

`|`

`&`

Evaluate all arguments as long integers using `strtol` and apply the logical operators NOT, OR or AND. The NOT operator works on the last argument only.

`/definq name var`

Use content of the variable *var* for inquiries with *name*. *name* may be an asterisk (*) to match any inquiry.

`/definqfile name file`

Use content of *file* for inquiries with *name*. *name* may be an asterisk (*) to match any inquiry.

`/definqprog name prog`

Run *prog* for inquiries matching *name* and pass the entire line to it as command line arguments.

`/datafile name`

Write all data lines from the server to the file *name*. The file is opened for writing and created if it does not exist. An existing file is first truncated to 0. The data written to the file fully decoded. Using a single dash for *name* writes to stdout. The file is kept open until a new file is set using this command or this command is used without an argument.

`/showdef` Print all definitions

`/cleardef`

Delete all definitions

/sendfd *file mode*
 Open *file* in *mode* (which needs to be a valid **fopen** mode string) and send the file descriptor to the server. This is usually followed by a command like **INPUT FD** to set the input source for other commands.

/recvfd Not yet implemented.

/open var *file* [*mode*]
 Open *file* and assign the file descriptor to *var*. Warning: This command is experimental and might change in future versions.

/close *fd*
 Close the file descriptor *fd*. Warning: This command is experimental and might change in future versions.

/showopen
 Show a list of open files.

/serverpid
 Send the Assuan command **GETINFO pid** to the server and store the returned PID for internal purposes.

/sleep Sleep for a second.

/hex

/nohex Same as the command line option ‘**--hex**’.

/decode

/nodecode
 Same as the command line option ‘**--decode**’.

/subst

/nosubst Enable and disable variable substitution. It defaults to disabled unless the command line option ‘**--subst**’ has been used. If **/subst** has been enabled once, leading whitespace is removed from input lines which makes scripts easier to read.

/while *condition*

/end These commands provide a way for executing loops. All lines between the **while** and the corresponding **end** are executed as long as the evaluation of *condition* yields a non-zero value or is the string **true** or **yes**. The evaluation is done by passing *condition* to the **strtol** function. Example:

```

    /subst
    /let i 3
    /while $i
      /echo loop counter is $i
      /let i ${- $i 1}
    /end

```

/if *condition*

/end These commands provide a way for conditional execution. All lines between the **if** and the corresponding **end** are executed only if the evaluation of *condition* yields a non-zero value or is the string **true** or **yes**. The evaluation is done by passing *condition* to the **strtol** function.

`/run file` Run commands from *file*.

`/bye` Terminate the connection and the program.

`/help` Print a list of available control commands.

9.8 The Dirmngr Client Tool

The `dirmngr-client` is a simple tool to contact a running `dirmngr` and test whether a certificate has been revoked — either by being listed in the corresponding CRL or by running the OCSP protocol. If no `dirmngr` is running, a new instances will be started but this is in general not a good idea due to the huge performance overhead.

The usual way to run this tool is either:

```
dirmngr-client acert
or
dirmngr-client <acert
```

Where *acert* is one DER encoded (binary) X.509 certificates to be tested. The return value of this command is

- 0 The certificate under question is valid; i.e. there is a valid CRL available and it is not listed there or the OCSP request returned that that certificate is valid.
- 1 The certificate has been revoked
- 2 (and other values) There was a problem checking the revocation state of the certificate. A message to `stderr` has given more detailed information. Most likely this is due to a missing or expired CRL or due to a network problem.

`dirmngr-client` may be called with the following options:

```
--version
    Print the program version and licensing information. Note that you cannot
    abbreviate this command.

--help, -h
    Print a usage message summarizing the most useful command-line options.
    Note that you cannot abbreviate this command.

--quiet, -q
    Make the output extra brief by suppressing any informational messages.

-v
--verbose
    Outputs additional information while running. You can increase the verbosity
    by giving several verbose commands to DIRMNGR, such as ‘-vv’.

--pem
    Assume that the given certificate is in PEM (armored) format.

--ocsp
    Do the check using the OCSP protocol and ignore any CRLs.
```

- force-default-responder**
When checking using the OCSP protocol, force the use of the default OCSP responder. That is not to use the Reponder as given by the certificate.
- ping** Check whether the dirmngr daemon is up and running.
- cache-cert**
Put the given certificate into the cache of a running dirmngr. This is mainly useful for debugging.
- validate**
Validate the given certificate using dirmngr's internal validation code. This is mainly useful for debugging.
- load-crl**
This command expects a list of filenames with DER encoded CRL files. With the option '**--url**' URLs are expected in place of filenames and they are loaded directly from the given location. All CRLs will be validated and then loaded into dirmngr's cache.
- lookup** Take the remaining arguments and run a lookup command on each of them. The results are Base-64 encoded outputs (without header lines). This may be used to retrieve certificates from a server. However the output format is not very well suited if more than one certificate is returned.
- url**
- u** Modify the **lookup** and **load-crl** commands to take an URL.
- local**
- l** Let the **lookup** command only search the local cache.
- squid-mode**
Run **DIRMNGR-CLIENT** in a mode suitable as a helper program for Squid's '**external_acl_type**' option.

9.9 Parse a mail message into an annotated format

The **gpgparsemail** is a utility currently only useful for debugging. Run it with **--help** for usage information.

9.10 Call a simple symmetric encryption tool

Sometimes simple encryption tools are already in use for a long time and there might be a desire to integrate them into the GnuPG framework. The protocols and encryption methods might be non-standard or not even properly documented, so that a full-fledged encryption tool with an interface like **gpg** is not doable. **symcryptrun** provides a solution: It operates by calling the external encryption/decryption module and provides a passphrase for a key using the standard **pinentry** based mechanism through **gpg-agent**.

Note, that **symcryptrun** is only available if GnuPG has been configured with '**--enable-symcryptrun**' at build time.

9.10.1 List of all commands and options

`symcryptrun` is invoked this way:

```
symcryptrun --class CLASS --program PROGRAM --keyfile KEYFILE
            [--decrypt | --encrypt] [inputfile]
```

For encryption, the plain text must be provided on STDIN or as the argument *inputfile*, and the ciphertext will be output to STDOUT. For decryption vice versa.

CLASS describes the calling conventions of the external tool. Currently it must be given as ‘`confucius`’. *PROGRAM* is the full filename of that external tool.

For the class ‘`confucius`’ the option ‘`--keyfile`’ is required; *keyfile* is the name of a file containing the secret key, which may be protected by a passphrase. For detailed calling conventions, see the source code.

Note, that `gpg-agent` must be running before starting `symcryptrun`.

The following additional options may be used:

`-v`

`--verbose`

Output additional information while running.

`-q`

`--quiet` Try to be as quiet as possible.

`--homedir dir`

Set the name of the home directory to *dir*. If this option is not used, the home directory defaults to ‘`~/.gnupg`’. It is only recognized when given on the command line. It also overrides any home directory stated through the environment variable `GNUPGHOME` or (on Windows systems) by means of the Registry entry `HKCU\Software\GNU\GnuPG:HomeDir`.

On Windows systems it is possible to install GnuPG as a portable application. In this case only this command line option is considered, all other ways to set a home directory are ignored.

To install GnuPG as a portable application under Windows, create an empty file named ‘`gpgconf.ct1`’ in the same directory as the tool ‘`gpgconf.exe`’. The root of the installation is then that directory; or, if ‘`gpgconf.exe`’ has been installed directly below a directory named ‘`bin`’, its parent directory. You also need to make sure that the following directories exist and are writable: ‘`ROOT/home`’ for the GnuPG home and ‘`ROOT/var/cache/gnupg`’ for internal cache files.

`--log-file file`

Append all logging output to *file*. Use ‘`socket://`’ to log to socket. Default is to write logging information to STDERR.

The possible exit status codes of `symcryptrun` are:

- | | |
|---|---|
| 0 | Success. |
| 1 | Some error occurred. |
| 2 | No valid passphrase was provided. |
| 3 | The operation was canceled by the user. |

9.11 Encrypt or sign files into an archive

gpgtar encrypts or signs files into an archive. It is an gpg-ized tar using the same format as used by PGP's PGP Zip.

gpgtar is invoked this way:

```
gpgtar [options] filename1 [filename2, ...] directory [directory2, ...]
```

gpgtar understands these options:

- create** Put given files and directories into a vanilla “ustar” archive.
- extract**
Extract all files from a vanilla “ustar” archive.
- encrypt**
- e** Encrypt given files and directories into an archive. This option may be combined with option ‘**--symmetric**’ for an archive that may be decrypted via a secret key or a passphrase.
- decrypt**
- d** Extract all files from an encrypted archive.
- sign**
- s** Make a signed archive from the given files and directories. This can be combined with option ‘**--encrypt**’ to create a signed and then encrypted archive.
- list-archive**
- t** List the contents of the specified archive.
- symmetric**
- c** Encrypt with a symmetric cipher using a passphrase. The default symmetric cipher used is AES-128, but may be chosen with the ‘**--cipher-algo**’ option to **gpg**.
- recipient user**
- r user** Encrypt for user id *user*. For details see **gpg**.
- local-user user**
- u user** Use *user* as the key to sign with. For details see **gpg**.
- output file**
- o file** Write the archive to the specified file *file*.
- verbose**
- v** Enable extra informational output.
- quiet**
- q** Try to be as quiet as possible.
- skip-crypto**
Skip all crypto operations and create or extract vanilla “ustar” archives.
- dry-run**
Do not actually output the extracted files.

- `--directory dir`
- `-C dir` Extract the files into the directory *dir*. The default is to take the directory name from the input filename. If no input filename is known a directory named 'GPGARCH' is used. For tarball creation, switch to directory *dir* before performing any operations.
- `--files-from file`
- `-T file` Take the file names to work from the file *file*; one file per line.
- `--null` Modify option '`--files-from`' to use a binary nul instead of a linefeed to separate file names.
- `--utf8-strings`
Assume that the file names read by '`--files-from`' are UTF-8 encoded. This option has an effect only on Windows where the active code page is otherwise assumed.
- `--openpgp`
This option has no effect because OpenPGP encryption and signing is the default.
- `--cms` This option is reserved and shall not be used. It will eventually be used to encrypt or sign using the CMS protocol; but that is not yet implemented.
- `--set-filename file`
Use the last component of *file* as the output directory. The default is to take the directory name from the input filename. If no input filename is known a directory named 'GPGARCH' is used. This option is deprecated in favor of option '`--directory`'.
- `--gpg gpgcmd`
Use the specified command *gpgcmd* instead of `gpg`.
- `--gpg-args args`
Pass the specified extra options to `gpg`.
- `--tar-args args`
Assume *args* are standard options of the command `tar` and parse them. The only supported tar options are "`--directory`", "`--files-from`", and "`--null`". This is an obsolete options because those supported tar options can also be given directly.
- `--version`
Print version of the program and exit.
- `--help` Display a brief help page and exit.

The program returns 0 if everything was fine, 1 otherwise.

Some examples:

Encrypt the contents of directory 'mydocs' for user Bob to file 'test1':

```
gpgtar --encrypt --output test1 -r Bob mydocs
```

List the contents of archive 'test1':

```
gpgtar --list-archive test1
```

10 Web Key Service

GnuPG comes with tools used to maintain and access a Web Key Directory.

10.1 Send requests via WKS

The `gpg-wks-client` is used to send requests to a Web Key Service provider. This is usually done to upload a key into a Web Key Directory.

With the `--supported` command the caller can test whether a site supports the Web Key Service. The argument is an arbitrary address in the to be tested domain. For example `foo@example.net`. The command returns success if the Web Key Service is supported. The operation is silent; to get diagnostic output use the option `--verbose`. See option `--with-colons` for a variant of this command.

With the `--check` command the caller can test whether a key exists for a supplied mail address. The command returns success if a key is available.

The `--create` command is used to send a request for publication in the Web Key Directory. The arguments are the fingerprint of the key and the user id to publish. The output from the command is a properly formatted mail with all standard headers. This mail can be fed to `sendmail(8)` or any other tool to actually send that mail. If `sendmail(8)` is installed the option `--send` can be used to directly send the created request. If the provider request a 'mailbox-only' user id and no such user id is found, `gpg-wks-client` will try an additional user id.

The `--receive` and `--read` commands are used to process confirmation mails as send from the service provider. The former expects an encrypted MIME messages, the latter an already decrypted MIME message. The result of these commands are another mail which can be send in the same way as the mail created with `--create`.

The command `--install-key` manually installs a key into a local directory (see option `-C`) reflecting the structure of a WKD. The arguments are a file with the keyblock and the user-id to install. If the first argument resembles a fingerprint the key is taken from the current keyring; to force the use of a file, prefix the first argument with `./`. If no arguments are given the parameters are read from stdin; the expected format are lines with the fingerprint and the mailbox separated by a space. The command `--remove-key` removes a key from that directory, its only argument is a user-id.

The command `--print-wkd-hash` prints the WKD user-id identifiers and the corresponding mailboxes from the user-ids given on the command line or via stdin (one user-id per line).

The command `--print-wkd-url` prints the URLs used to fetch the key for the given user-ids from WKD. The meanwhile preferred format with sub-domains is used here.

`gpg-wks-client` is not commonly invoked directly and thus it is not installed in the bin directory. Here is an example how it can be invoked manually to check for a Web Key Directory entry for `foo@example.org`:

```
$(gpgconf --list-dirs libexecdir)/gpg-wks-client --check foo@example.net
```

`gpg-wks-client` understands these options:

`--send` Directly send created mails using the `sendmail` command. Requires installation of that command.

--with-colons

This option has currently only an effect on the ‘**--supported**’ command. If it is used all arguments on the command line are taken as domain names and tested for WKD support. The output format is one line per domain with colon delimited fields. The currently specified fields are (future versions may specify additional fields):

1 - domain

This is the domain name. Although quoting is not required for valid domain names this field is specified to be quoted in standard C manner.

2 - WKD If the value is true the domain supports the Web Key Directory.

3 - WKS If the value is true the domain supports the Web Key Service protocol to upload keys to the directory.

4 - error-code

This may contain an gpg-error code to describe certain failures. Use ‘**gpg-error CODE**’ to explain the code.

5 - protocol-version

The minimum protocol version supported by the server.

6 - auth-submit

The auth-submit flag from the policy file of the server.

7 - mailbox-only

The mailbox-only flag from the policy file of the server.

--output *file*

-o Write the created mail to *file* instead of stdout. Note that the value - for *file* is the same as writing to stdout.

--status-fd *n*

Write special status strings to the file descriptor *n*. This program returns only the status messages SUCCESS or FAILURE which are helpful when the caller uses a double fork approach and can’t easily get the return code of the process.

-C *dir***--directory *dir***

Use *dir* as top level directory for the commands ‘**--install-key**’ and ‘**--remove-key**’. The default is ‘**openpgpkey**’.

--verbose

Enable extra informational output.

--quiet Disable almost all informational output.

--version

Print version of the program and exit.

--help Display a brief help page and exit.

10.2 Provide the Web Key Service

The `gpg-wks-server` is a server site implementation of the Web Key Service. It receives requests for publication, sends confirmation requests, receives confirmations, and publishes the key. It also has features to ease the setup and maintenance of a Web Key Directory.

When used with the command '`--receive`' a single Web Key Service mail is processed. Commonly this command is used with the option '`--send`' to directly send the created mails back. See below for an installation example.

The command '`--cron`' is used for regular cleanup tasks. For example non-confirmed requests should be removed after their expire time. It is best to run this command once a day from a cronjob.

The command '`--list-domains`' prints all configured domains. Further it creates missing directories for the configuration and prints warnings pertaining to problems in the configuration.

The command '`--check-key`' (or just '`--check`') checks whether a key with the given user-id is installed. The process returns success in this case; to also print a diagnostic use the option '`-v`'. If the key is not installed a diagnostic is printed and the process returns failure; to suppress the diagnostic, use option '`-q`'. More than one user-id can be given; see also option '`with-file`'.

The command '`--install-key`' manually installs a key into the WKD. The arguments are a file with the keyblock and the user-id to install. If the first argument resembles a fingerprint the key is taken from the current keyring; to force the use of a file, prefix the first argument with `./`. If no arguments are given the parameters are read from stdin; the expected format are lines with the fingerprint and the mailbox separated by a space.

The command '`--remove-key`' uninstalls a key from the WKD. The process returns success in this case; to also print a diagnostic, use option '`-v`'. If the key is not installed a diagnostic is printed and the process returns failure; to suppress the diagnostic, use option '`-q`'.

The command '`--revoke-key`' is not yet functional.

`gpg-wks-server` understands these options:

```
-C dir
--directory dir
    Use dir as top level directory for domains.      The default is
    '/var/lib/gnupg/wks'.

--from mailaddr
    Use mailaddr as the default sender address.

--header name=value
    Add the mail header "name: value" to all outgoing mails.

--send      Directly send created mails using the sendmail command. Requires installation
            of that command.

-o file
--output file
    Write the created mail also to file. Note that the value - for file would write it
    to stdout.
```

--with-dir When used with the command '**--list-domains**' print for each installed domain the domain name and its directory name.

--with-file When used with the command '**--check-key**' print for each user-id, the address, 'i' for installed key or 'n' for not installed key, and the filename.

--verbose Enable extra informational output.

--quiet Disable almost all informational output.

--version Print version of the program and exit.

--help Display a brief help page and exit.

Examples

The Web Key Service requires a working directory to store keys pending for publication. As root create a working directory:

```
# mkdir /var/lib/gnupg/wks
# chown webkey:webkey /var/lib/gnupg/wks
# chmod 2750 /var/lib/gnupg/wks
```

Then under your webkey account create directories for all your domains. Here we do it for "example.net":

```
$ mkdir /var/lib/gnupg/wks/example.net
```

Finally run

```
$ gpg-wks-server --list-domains
```

to create the required sub-directories with the permissions set correctly. For each domain a submission address needs to be configured. All service mails are directed to that address. It can be the same address for all configured domains, for example:

```
$ cd /var/lib/gnupg/wks/example.net
$ echo key-submission@example.net >submission-address
```

The protocol requires that the key to be published is send with an encrypted mail to the service. Thus you need to create a key for the submission address:

```
$ gpg --batch --passphrase '' --quick-gen-key key-submission@example.net
$ gpg -K key-submission@example.net
```

The output of the last command looks similar to this:

```
sec  rsa2048 2016-08-30 [SC]
      C0FCF8642D830C53246211400346653590B3795B
uid  [ultimate] key-submission@example.net
ssb  rsa2048 2016-08-30 [E]
```

Take the fingerprint from that output and manually publish the key:

```
$ gpg-wks-server --install-key C0FCF8642D830C53246211400346653590B3795B \
> key-submission@example.net
```

Finally that submission address needs to be redirected to a script running `gpg-wks-server`. The `procmail` command can be used for this: Redirect the submission address to the user "webkey" and put this into webkey's `.procmailrc`:

```
:0
* !^From: webkey@example.net
* !^X-WKS-Loop: webkey.example.net
|gpg-wks-server -v --receive \
  --header X-WKS-Loop=webkey.example.net \
  --from webkey@example.net --send
```


11 How to do certain things

This is a collection of small howto documents.

11.1 Creating a TLS server certificate

Here is a brief run up on how to create a server certificate. It has actually been done this way to get a certificate from CAcert to be used on a real server. It has only been tested with this CA, but there shouldn't be any problem to run this against any other CA.

We start by generating an X.509 certificate signing request. As there is no need for a configuration file, you may simply enter:

```
$ gpgsm --generate-key >example.com.cert-req.pem
Please select what kind of key you want:
  (1) RSA
  (2) Existing key
  (3) Existing key from card
Your selection? 1
```

I opted for creating a new RSA key. The other option is to use an already existing key, by selecting 2 and entering the so-called keygrip. Running the command '`gpgsm --dump-secret-key USERID`' shows you this keygrip. Using 3 offers another menu to create a certificate directly from a smart card based key.

Let's continue:

```
What keysize do you want? (3072)
Requested keysize is 3072 bits
```

Hitting enter chooses the default RSA key size of 3072 bits. Keys smaller than 2048 bits are too weak on the modern Internet. If you choose a larger (stronger) key, your server will need to do more work.

```
Possible actions for a RSA key:
  (1) sign, encrypt
  (2) sign
  (3) encrypt
Your selection? 1
```

Selecting "sign" enables use of the key for Diffie-Hellman key exchange mechanisms (DHE and ECDHE) in TLS, which are preferred because they offer forward secrecy. Selecting "encrypt" enables RSA key exchange mechanisms, which are still common in some places. Selecting both enables both key exchange mechanisms.

Now for some real data:

```
Enter the X.509 subject name: CN=example.com
```

This is the most important value for a server certificate. Enter here the canonical name of your server machine. You may add other virtual server names later.

```
E-Mail addresses (end with an empty line):  
>
```

We don't need email addresses in a TLS server certificate and CAcert would anyway ignore such a request. Thus just hit enter.

If you want to create a client certificate for email encryption, this would be the place to enter your mail address (e.g. joe@example.org). You may enter as many addresses as you like, however the CA may not accept them all or reject the entire request.

```
Enter DNS names (optional; end with an empty line):  
> example.com  
> www.example.com  
>
```

Here I entered the names of the services which the machine actually provides. You almost always want to include the canonical name here too. The browser will accept a certificate for any of these names. As usual the CA must approve all of these names.

```
URIs (optional; end with an empty line):  
>
```

It is possible to insert arbitrary URIs into a certificate; for a server certificate this does not make sense.

```
Create self-signed certificate? (y/N)
```

Since we are creating a certificate signing request, and not a full certificate, we answer no here, or just hit enter for the default.

We have now entered all required information and `gpgsm` will display what it has gathered and ask whether to create the certificate request:

```
These parameters are used:  
  Key-Type: RSA  
  Key-Length: 3072  
  Key-Usage: sign, encrypt  
  Name-DN: CN=example.com  
  Name-DNS: example.com  
  Name-DNS: www.example.com  
  
Proceed with creation? (y/N) y
```

`gpgsm` will now start working on creating the request. As this includes the creation of an RSA key it may take a while. During this time you will be asked 3 times for a passphrase to protect the created private key on your system. A pop up window will appear to ask for it. The first two prompts are for the new passphrase and for re-entering it; the third one is required to actually create the certificate signing request.

When it is ready, you should see the final notice:

```
Ready. You should now send this request to your CA.
```

Now, you may look at the created request:

```
$ cat example.com.cert-req.pem
-----BEGIN CERTIFICATE REQUEST-----
MIIC1TCCAQAQAwFjEUMBIGA1UEAxMLZXhhbXBsZS5jb20wggEiMA0GCSqGSIb3
DQEBAQUAA4IBDwAwggEKAoIBAQDP1QEcbTvOLLCX4gAoOzH9AW7jNOMj7OSOL0uW
h2bCdkK5YVpnX212Z6COTC3ZG0pJiCeGt1TbbDJU1Ta4syQ6JXavjK66N8ASZsyC
Rwcl0m6hbXp541t1dbgt2VgeGk25okWw3j+brw6zxLD2TnthJx0atID01DIG47HW
GqzZmA6WHbIBIONmGnReIHTpPAPCDm92vUkpKG1xLPszuRmsQbwE1870W/FHrsvm
DPvVUUSdIvTV9NuRt7/WY6G4nPP9Q1IuTf1ESPzIuIE91gKPdrRCAX0yuT708S1n
xCv3ETQ/bKPoAQ67eE3mPBqkcVwv9SE/2/36Lz06kAizRgs5AgMBAAGg0jA4Bgkq
hkiG9w0BCQ4xKzApMCCGA1UdEQQgMB6CC2V4YW1wbGUuY29tgg93d3cuZXhhbXBs
ZS5jb20wDQYJKoZIhvcNAQELBQADggEBAEWD0Qqz40ENLYp6yy0/KqF0ig9FDsLN
b5/R+qhms5qlhdB5+Dh+j693Sj0UgbcNKc6JT86IuBqEBZmRCJuXR0Koo5aMS1cJ
hXga7N9IA3qb4VBuzBWv1L92U2Iptr/cEbikF1YZF2Zv3PBv8RfopV1I30LbKV9D
bJJTt/6kuoydXKo/Vx4G0DFzIKNdFdJk86o/Ziz8N0s9JjZxw9H9VY5sHKFM5LKk
VcLwnnLR1NjBGB+9VK/Tze575eG0cJomTp7UGIB+1xzIQVAhUZ0izRDv9tHDeaK3
k+tUhV0kuJcYHucpJycDSrP/uAY5zuVJ0rs2QSjdnav62YrRgEsxJrU=
-----END CERTIFICATE REQUEST-----
$
```

You may now proceed by logging into your account at the CAcert website, choose **Server Certificates - New**, check **sign by class 3 root certificate**, paste the above request block into the text field and click on **Submit**.

If everything works out fine, a certificate will be shown. Now run

```
$ gpgsm --import
```

and paste the certificate from the CAcert page into your terminal followed by a Ctrl-D

```

-----BEGIN CERTIFICATE-----
MIIEljCCAgqgAwIBAgIBTDANBgkqhkiG9w0BAQQFADBUMRQwEgYDVQQKEwtDQWN1
[...]
rUTF1NElRXCWIl0YcJkIaYYqWf7+A/aqYJCi8+51usZwMy3JsQ3hJ6MA3h1BgwZs
Rtct3tIX
-----END CERTIFICATE-----
gpgsm: issuer certificate (#/CN=CACert Class 3 Ro[...]) not found
gpgsm: certificate imported

gpgsm: total number processed: 1
gpgsm:                imported: 1

```

gpgsm tells you that it has imported the certificate. It is now associated with the key you used when creating the request. The root certificate has not been found, so you may want to import it from the CACert website.

To see the content of your certificate, you may now enter:

```

$ gpgsm -K example.com
/home/foo/.gnupg/pubring.kbx
-----
Serial number: 4C
    Issuer: /CN=CACert Class 3 Root/OU=http:\x2f\x2fwww.[...]
    Subject: /CN=example.com
        aka: (dns-name example.com)
        aka: (dns-name www.example.com)
    validity: 2015-07-01 16:20:51 through 2016-07-01 16:20:51
    key type: 3072 bit RSA
    key usage: digitalSignature keyEncipherment
ext key usage: clientAuth (suggested), serverAuth (suggested), [...]
    fingerprint: 0F:9C:27:B2:DA:05:5F:CB:33:D8:19:E9:65:B9:4F:BD:B1:98:CC:57

```

I used ‘-K’ above because this will only list certificates for which a private key is available. To see more details, you may use ‘--dump-secret-keys’ instead of ‘-K’.

To make actual use of the certificate you need to install it on your server. Server software usually expects a PKCS\#12 file with key and certificate. To create such a file, run:

```
$ gpgsm --export-secret-key-p12 -a >example.com-cert.pem
```

You will be asked for the passphrase as well as for a new passphrase to be used to protect the PKCS\#12 file. The file now contains the certificate as well as the private key:

```
$ cat example-cert.pem
Issuer ...: /CN=CAcert Class 3 Root/OU=http:\x2f\x2fwww.CA[...]
Serial ...: 4C
Subject ..: /CN=example.com
          aka ..: (dns-name example.com)
          aka ..: (dns-name www.example.com)

-----BEGIN PKCS12-----
MIIHlwIBAzCCB5AGCSqGSib37QdHAaCCB4EEg9d9MIIHeTk1BJ8GCSqGSib3DQEu
[...many more lines...]
-----END PKCS12-----
$
```

Copy this file in a secure way to the server, install it there and delete the file then. You may export the file again at any time as long as it is available in GnuPG's private key database.

12 Notes pertaining to certain OSes

GnuPG has been developed on GNU/Linux systems and is known to work on almost all Free OSes. All modern POSIX systems should be supported right now, however there are probably a lot of smaller glitches we need to fix first. The major problem areas are:

- We are planning to use file descriptor passing for interprocess communication. This will allow us save a lot of resources and improve performance of certain operations a lot. Systems not supporting this won't gain these benefits but we try to keep them working the standard way as it is done today.
- We require more or less full POSIX compatibility. This has been around for 15 years now and thus we don't believe it makes sense to support non POSIX systems anymore. Well, we of course the usual workarounds for near POSIX systems will be applied.

There is one exception of this rule: Systems based the Microsoft Windows API (called here *W32*) will be supported to some extend.

12.1 Microsoft Windows Notes

Current limitations are:

- `gpgconf` does not create backup files, so in case of trouble your configuration file might get lost.
- `watchgnupg` is not available. Logging to sockets is not possible.
- The periodical smartcard status checking done by `scdaemon` is not yet supported.

13 How to solve problems

Everyone knows that software often does not do what it should do and thus there is a need to track down problems. We call this debugging in a reminiscent to the moth jamming a relay in a Mark II box back in 1947.

Most of the problems are merely configuration and user problems but nevertheless they are the most annoying ones and responsible for many gray hairs. We try to give some guidelines here on how to identify and solve the problem at hand.

13.1 Debugging Tools

The GnuPG distribution comes with a couple of tools, useful to help find and solving problems.

13.1.1 Scrutinizing a keybox file

A keybox is a file format used to store public keys along with meta information and indices. The commonly used one is the file `'pubring.kbx'` in the `'gnupg'` directory. It contains all X.509 certificates as well as OpenPGP keys.

When called the standard way, e.g.:

```
'kbxutil ~/.gnupg/pubring.kbx'
```

it lists all records (called blobs) with their meta-information in a human readable format.

To see statistics on the keybox in question, run it using

```
'kbxutil --stats ~/.gnupg/pubring.kbx'
```

and you get an output like:

```

Total number of blobs:      99
      header:                1
      empty:                 0
      openpgp:               0
      x509:                  98
      non flagged:           81
      secret flagged:        0
      ephemeral flagged:     17
```

In this example you see that the keybox does not have any OpenPGP keys but contains 98 X.509 certificates and a total of 17 keys or certificates are flagged as ephemeral, meaning that they are only temporarily stored (cached) in the keybox and won't get listed using the usual commands provided by `gpgsm` or `gpg`. 81 certificates are stored in a standard way and directly available from `gpgsm`.

To find duplicated certificates and keyblocks in a keybox file (this should not occur but sometimes things go wrong), run it using

```
'kbxutil --find-dups ~/.gnupg/pubring.kbx'
```

13.2 Various hints on debugging

- How to find the IP address of a keyserver

If a round robin URL of is used for a keyserver (e.g. `subkeys.gnupg.org`); it is not easy to see what server is actually used. Using the keyserver debug option as in

```
gpg --keyserver-options debug=1 -v --refresh-key 1E42B367
```

is thus often helpful. Note that the actual output depends on the backend and may change from release to release.

- Logging on WindowsCE

For development, the best logging method on WindowsCE is the use of remote debugging using a log file name of `'tcp://<ip-addr>:<port>'`. The command `watchgnupg` may be used on the remote host to listen on the given port (see [option `watchgnupg -tcp`], page 135). For in the field tests it is better to make use of the logging facility provided by the `gpgcdev` driver (part of `libassuan`); this is enabled by using a log file name of `'GPG2:'` (see [option `-log-file`], page 6).

13.3 Commonly Seen Problems

- Error code `'Not supported'` from `Dirmngr`

Most likely the option `'enable-ocsp'` is active for `gpgsm` but `Dirmngr`'s OCSP feature has not been enabled using `'allow-ocsp'` in `'dirmngr.conf'`.

- The Curses based Pinentry does not work

The far most common reason for this is that the environment variable `GPG_TTY` has not been set correctly. Make sure that it has been set to a real tty device and not just to `'/dev/tty'`; i.e. `'GPG_TTY=tty'` is plainly wrong; what you want is `'GPG_TTY='tty''` — note the back ticks. Also make sure that this environment variable gets exported, that is you should follow up the setting with an `'export GPG_TTY'` (assuming a Bourne style shell). Even for GUI based Pinentries; you should have set `GPG_TTY`. See the section on installing the `gpg-agent` on how to do it.

- SSH hangs while a popping up pinentry was expected

SSH has no way to tell the `gpg-agent` what terminal or X display it is running on. So when remotely logging into a box where a `gpg-agent` with SSH support is running, the pinentry will get popped up on whatever display the `gpg-agent` has been started. To solve this problem you may issue the command

```
echo UPDATESTARTUPTTY | gpg-connect-agent
```

and the next pinentry will pop up on your display or screen. However, you need to kill the running pinentry first because only one pinentry may be running at once. If you plan to use `ssh` on a new display you should issue the above command before invoking `ssh` or any other service making use of `ssh`.

- Exporting a secret key without a certificate

It may happen that you have created a certificate request using `gpgsm` but not yet received and imported the certificate from the CA. However, you want to export the secret key to another machine right now to import the certificate over there then. You can do this with a little trick but it requires that you know the approximate time you created the signing request. By running the command

```
ls -ltr ~/.gnupg/private-keys-v1.d
```

you get a listing of all private keys under control of **gpg-agent**. Pick the key which best matches the creation time and run the command

```
/usr/libexec/gpg-protect-tool --p12-export \
~/.gnupg/private-keys-v1.d/foo >foo.p12
```

(Please adjust the path to **gpg-protect-tool** to the appropriate location). *foo* is the name of the key file you picked (it should have the suffix `.key`). A Pinentry box will pop up and ask you for the current passphrase of the key and a new passphrase to protect it in the pkcs#12 file.

To import the created file on the machine you use this command:

```
/usr/libexec/gpg-protect-tool --p12-import --store foo.p12
```

You will be asked for the pkcs#12 passphrase and a new passphrase to protect the imported private key at its new location.

Note that there is no easy way to match existing certificates with stored private keys because some private keys are used for Secure Shell or other purposes and don't have a corresponding certificate.

- A root certificate does not verify

A common problem is that the root certificate misses the required `basicConstraints` attribute and thus **gpgsm** rejects this certificate. An error message indicating “no value” is a sign for such a certificate. You may use the `relax` flag in `trustlist.txt` to accept the certificate anyway. Note that the fingerprint and this flag may only be added manually to `trustlist.txt`.

- Error message: “digest algorithm N has not been enabled”

The signature is broken. You may try the option `--extra-digest-algo SHA256` to workaround the problem. The number N is the internal algorithm identifier; for example 8 refers to SHA-256.

- The Windows version does not work under Wine

When running the W32 version of **gpg** under Wine you may get an error messages like:

```
gpg: fatal: WriteConsole failed: Access denied
```

The solution is to use the command **wineconsole**.

Some operations like `--generate-key` really want to talk to the console directly for increased security (for example to prevent the passphrase from appearing on the screen). So, you should use **wineconsole** instead of **wine**, which will launch a windows console that implements those additional features.

- Why does GPG's `--search-key` list weird keys?

For performance reasons the key servers do not check the keys the same way **gpg** does. It may happen that the listing of keys available on the key servers shows keys with wrong user IDs or with user IDs from other keys. If you try to import this key, the bad keys or bad user IDs won't get imported, though. This is a bit unfortunate but we can't do anything about it without actually downloading the keys.

13.4 How the whole thing works internally

13.4.1 How the components work together



Figure 13.1: GnuPG module overview

13.4.2 Relationship between GnuPG 1.4 and 2.x

Here is a little picture showing how the different GnuPG versions make use of a smartcard:



Figure 13.2: GnuPG card architecture

GNU General Public License

Version 3, 29 June 2007

Copyright © 2007 Free Software Foundation, Inc. <https://fsf.org/>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

Preamble

The GNU General Public License is a free, copyleft license for software and other kinds of works.

The licenses for most software and other practical works are designed to take away your freedom to share and change the works. By contrast, the GNU General Public License is intended to guarantee your freedom to share and change all versions of a program—to make sure it remains free software for all its users. We, the Free Software Foundation, use the GNU General Public License for most of our software; it applies also to any other work released this way by its authors. You can apply it to your programs, too.

When we speak of free software, we are referring to freedom, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for them if you wish), that you receive source code or can get it if you want it, that you can change the software or use pieces of it in new free programs, and that you know you can do these things.

To protect your rights, we need to prevent others from denying you these rights or asking you to surrender the rights. Therefore, you have certain responsibilities if you distribute copies of the software, or if you modify it: responsibilities to respect the freedom of others.

For example, if you distribute copies of such a program, whether gratis or for a fee, you must pass on to the recipients the same freedoms that you received. You must make sure that they, too, receive or can get the source code. And you must show them these terms so they know their rights.

Developers that use the GNU GPL protect your rights with two steps: (1) assert copyright on the software, and (2) offer you this License giving you legal permission to copy, distribute and/or modify it.

For the developers' and authors' protection, the GPL clearly explains that there is no warranty for this free software. For both users' and authors' sake, the GPL requires that modified versions be marked as changed, so that their problems will not be attributed erroneously to authors of previous versions.

Some devices are designed to deny users access to install or run modified versions of the software inside them, although the manufacturer can do so. This is fundamentally incompatible with the aim of protecting users' freedom to change the software. The systematic pattern of such abuse occurs in the area of products for individuals to use, which is precisely where it is most unacceptable. Therefore, we have designed this version of the GPL to prohibit the practice for those products. If such problems arise substantially in other domains, we stand ready to extend this provision to those domains in future versions of the GPL, as needed to protect the freedom of users.

Finally, every program is threatened constantly by software patents. States should not allow patents to restrict development and use of software on general-purpose computers, but in those that do, we wish to avoid the special danger that patents applied to a free program could make it effectively proprietary. To prevent this, the GPL assures that patents cannot be used to render the program non-free.

The precise terms and conditions for copying, distribution and modification follow.

TERMS AND CONDITIONS

0. Definitions.

“This License” refers to version 3 of the GNU General Public License.

“Copyright” also means copyright-like laws that apply to other kinds of works, such as semiconductor masks.

“The Program” refers to any copyrightable work licensed under this License. Each licensee is addressed as “you”. “Licensees” and “recipients” may be individuals or organizations.

To “modify” a work means to copy from or adapt all or part of the work in a fashion requiring copyright permission, other than the making of an exact copy. The resulting work is called a “modified version” of the earlier work or a work “based on” the earlier work.

A “covered work” means either the unmodified Program or a work based on the Program.

To “propagate” a work means to do anything with it that, without permission, would make you directly or secondarily liable for infringement under applicable copyright law, except executing it on a computer or modifying a private copy. Propagation includes copying, distribution (with or without modification), making available to the public, and in some countries other activities as well.

To “convey” a work means any kind of propagation that enables other parties to make or receive copies. Mere interaction with a user through a computer network, with no transfer of a copy, is not conveying.

An interactive user interface displays “Appropriate Legal Notices” to the extent that it includes a convenient and prominently visible feature that (1) displays an appropriate copyright notice, and (2) tells the user that there is no warranty for the work (except to the extent that warranties are provided), that licensees may convey the work under this License, and how to view a copy of this License. If the interface presents a list of user commands or options, such as a menu, a prominent item in the list meets this criterion.

1. Source Code.

The “source code” for a work means the preferred form of the work for making modifications to it. “Object code” means any non-source form of a work.

A “Standard Interface” means an interface that either is an official standard defined by a recognized standards body, or, in the case of interfaces specified for a particular programming language, one that is widely used among developers working in that language.

The “System Libraries” of an executable work include anything, other than the work as a whole, that (a) is included in the normal form of packaging a Major Component, but which is not part of that Major Component, and (b) serves only to enable use of the work with that Major Component, or to implement a Standard Interface for which an implementation is available to the public in source code form. A “Major Component”, in this context, means a major essential component (kernel, window system, and so on) of the specific operating system (if any) on which the executable work runs, or a compiler used to produce the work, or an object code interpreter used to run it.

The “Corresponding Source” for a work in object code form means all the source code needed to generate, install, and (for an executable work) run the object code and to modify the work, including scripts to control those activities. However, it does not include the work’s System Libraries, or general-purpose tools or generally available free programs which are used unmodified in performing those activities but which are not part of the work. For example, Corresponding Source includes interface definition files associated with source files for the work, and the source code for shared libraries and dynamically linked subprograms that the work is specifically designed to require, such as by intimate data communication or control flow between those subprograms and other parts of the work.

The Corresponding Source need not include anything that users can regenerate automatically from other parts of the Corresponding Source.

The Corresponding Source for a work in source code form is that same work.

2. Basic Permissions.

All rights granted under this License are granted for the term of copyright on the Program, and are irrevocable provided the stated conditions are met. This License explicitly affirms your unlimited permission to run the unmodified Program. The output from running a covered work is covered by this License only if the output, given its content, constitutes a covered work. This License acknowledges your rights of fair use or other equivalent, as provided by copyright law.

You may make, run and propagate covered works that you do not convey, without conditions so long as your license otherwise remains in force. You may convey covered works to others for the sole purpose of having them make modifications exclusively for you, or provide you with facilities for running those works, provided that you comply with the terms of this License in conveying all material for which you do not control copyright. Those thus making or running the covered works for you must do so exclusively on your behalf, under your direction and control, on terms that prohibit them from making any copies of your copyrighted material outside their relationship with you.

Conveying under any other circumstances is permitted solely under the conditions stated below. Sublicensing is not allowed; section 10 makes it unnecessary.

3. Protecting Users’ Legal Rights From Anti-Circumvention Law.

No covered work shall be deemed part of an effective technological measure under any applicable law fulfilling obligations under article 11 of the WIPO copyright treaty adopted on 20 December 1996, or similar laws prohibiting or restricting circumvention of such measures.

When you convey a covered work, you waive any legal power to forbid circumvention of technological measures to the extent such circumvention is effected by exercising rights under this License with respect to the covered work, and you disclaim any intention to limit operation or modification of the work as a means of enforcing, against the work's users, your or third parties' legal rights to forbid circumvention of technological measures.

4. Conveying Verbatim Copies.

You may convey verbatim copies of the Program's source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice; keep intact all notices stating that this License and any non-permissive terms added in accord with section 7 apply to the code; keep intact all notices of the absence of any warranty; and give all recipients a copy of this License along with the Program.

You may charge any price or no price for each copy that you convey, and you may offer support or warranty protection for a fee.

5. Conveying Modified Source Versions.

You may convey a work based on the Program, or the modifications to produce it from the Program, in the form of source code under the terms of section 4, provided that you also meet all of these conditions:

- a. The work must carry prominent notices stating that you modified it, and giving a relevant date.
- b. The work must carry prominent notices stating that it is released under this License and any conditions added under section 7. This requirement modifies the requirement in section 4 to "keep intact all notices".
- c. You must license the entire work, as a whole, under this License to anyone who comes into possession of a copy. This License will therefore apply, along with any applicable section 7 additional terms, to the whole of the work, and all its parts, regardless of how they are packaged. This License gives no permission to license the work in any other way, but it does not invalidate such permission if you have separately received it.
- d. If the work has interactive user interfaces, each must display Appropriate Legal Notices; however, if the Program has interactive interfaces that do not display Appropriate Legal Notices, your work need not make them do so.

A compilation of a covered work with other separate and independent works, which are not by their nature extensions of the covered work, and which are not combined with it such as to form a larger program, in or on a volume of a storage or distribution medium, is called an "aggregate" if the compilation and its resulting copyright are not used to limit the access or legal rights of the compilation's users beyond what the individual works permit. Inclusion of a covered work in an aggregate does not cause this License to apply to the other parts of the aggregate.

6. Conveying Non-Source Forms.

You may convey a covered work in object code form under the terms of sections 4 and 5, provided that you also convey the machine-readable Corresponding Source under the terms of this License, in one of these ways:

- a. Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by the Corresponding Source fixed on a durable physical medium customarily used for software interchange.
- b. Convey the object code in, or embodied in, a physical product (including a physical distribution medium), accompanied by a written offer, valid for at least three years and valid for as long as you offer spare parts or customer support for that product model, to give anyone who possesses the object code either (1) a copy of the Corresponding Source for all the software in the product that is covered by this License, on a durable physical medium customarily used for software interchange, for a price no more than your reasonable cost of physically performing this conveying of source, or (2) access to copy the Corresponding Source from a network server at no charge.
- c. Convey individual copies of the object code with a copy of the written offer to provide the Corresponding Source. This alternative is allowed only occasionally and noncommercially, and only if you received the object code with such an offer, in accord with subsection 6b.
- d. Convey the object code by offering access from a designated place (gratis or for a charge), and offer equivalent access to the Corresponding Source in the same way through the same place at no further charge. You need not require recipients to copy the Corresponding Source along with the object code. If the place to copy the object code is a network server, the Corresponding Source may be on a different server (operated by you or a third party) that supports equivalent copying facilities, provided you maintain clear directions next to the object code saying where to find the Corresponding Source. Regardless of what server hosts the Corresponding Source, you remain obligated to ensure that it is available for as long as needed to satisfy these requirements.
- e. Convey the object code using peer-to-peer transmission, provided you inform other peers where the object code and Corresponding Source of the work are being offered to the general public at no charge under subsection 6d.

A separable portion of the object code, whose source code is excluded from the Corresponding Source as a System Library, need not be included in conveying the object code work.

A “User Product” is either (1) a “consumer product”, which means any tangible personal property which is normally used for personal, family, or household purposes, or (2) anything designed or sold for incorporation into a dwelling. In determining whether a product is a consumer product, doubtful cases shall be resolved in favor of coverage. For a particular product received by a particular user, “normally used” refers to a typical or common use of that class of product, regardless of the status of the particular user or of the way in which the particular user actually uses, or expects or is expected to use, the product. A product is a consumer product regardless of whether the product has substantial commercial, industrial or non-consumer uses, unless such uses represent the only significant mode of use of the product.

“Installation Information” for a User Product means any methods, procedures, authorization keys, or other information required to install and execute modified versions of a covered work in that User Product from a modified version of its Corresponding Source.

The information must suffice to ensure that the continued functioning of the modified object code is in no case prevented or interfered with solely because modification has been made.

If you convey an object code work under this section in, or with, or specifically for use in, a User Product, and the conveying occurs as part of a transaction in which the right of possession and use of the User Product is transferred to the recipient in perpetuity or for a fixed term (regardless of how the transaction is characterized), the Corresponding Source conveyed under this section must be accompanied by the Installation Information. But this requirement does not apply if neither you nor any third party retains the ability to install modified object code on the User Product (for example, the work has been installed in ROM).

The requirement to provide Installation Information does not include a requirement to continue to provide support service, warranty, or updates for a work that has been modified or installed by the recipient, or for the User Product in which it has been modified or installed. Access to a network may be denied when the modification itself materially and adversely affects the operation of the network or violates the rules and protocols for communication across the network.

Corresponding Source conveyed, and Installation Information provided, in accord with this section must be in a format that is publicly documented (and with an implementation available to the public in source code form), and must require no special password or key for unpacking, reading or copying.

7. Additional Terms.

“Additional permissions” are terms that supplement the terms of this License by making exceptions from one or more of its conditions. Additional permissions that are applicable to the entire Program shall be treated as though they were included in this License, to the extent that they are valid under applicable law. If additional permissions apply only to part of the Program, that part may be used separately under those permissions, but the entire Program remains governed by this License without regard to the additional permissions.

When you convey a copy of a covered work, you may at your option remove any additional permissions from that copy, or from any part of it. (Additional permissions may be written to require their own removal in certain cases when you modify the work.) You may place additional permissions on material, added by you to a covered work, for which you have or can give appropriate copyright permission.

Notwithstanding any other provision of this License, for material you add to a covered work, you may (if authorized by the copyright holders of that material) supplement the terms of this License with terms:

- a. Disclaiming warranty or limiting liability differently from the terms of sections 15 and 16 of this License; or
- b. Requiring preservation of specified reasonable legal notices or author attributions in that material or in the Appropriate Legal Notices displayed by works containing it; or
- c. Prohibiting misrepresentation of the origin of that material, or requiring that modified versions of such material be marked in reasonable ways as different from the original version; or

- d. Limiting the use for publicity purposes of names of licensors or authors of the material; or
- e. Declining to grant rights under trademark law for use of some trade names, trademarks, or service marks; or
- f. Requiring indemnification of licensors and authors of that material by anyone who conveys the material (or modified versions of it) with contractual assumptions of liability to the recipient, for any liability that these contractual assumptions directly impose on those licensors and authors.

All other non-permissive additional terms are considered “further restrictions” within the meaning of section 10. If the Program as you received it, or any part of it, contains a notice stating that it is governed by this License along with a term that is a further restriction, you may remove that term. If a license document contains a further restriction but permits relicensing or conveying under this License, you may add to a covered work material governed by the terms of that license document, provided that the further restriction does not survive such relicensing or conveying.

If you add terms to a covered work in accord with this section, you must place, in the relevant source files, a statement of the additional terms that apply to those files, or a notice indicating where to find the applicable terms.

Additional terms, permissive or non-permissive, may be stated in the form of a separately written license, or stated as exceptions; the above requirements apply either way.

8. Termination.

You may not propagate or modify a covered work except as expressly provided under this License. Any attempt otherwise to propagate or modify it is void, and will automatically terminate your rights under this License (including any patent licenses granted under the third paragraph of section 11).

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, you do not qualify to receive new licenses for the same material under section 10.

9. Acceptance Not Required for Having Copies.

You are not required to accept this License in order to receive or run a copy of the Program. Ancillary propagation of a covered work occurring solely as a consequence of using peer-to-peer transmission to receive a copy likewise does not require acceptance.

However, nothing other than this License grants you permission to propagate or modify any covered work. These actions infringe copyright if you do not accept this License. Therefore, by modifying or propagating a covered work, you indicate your acceptance of this License to do so.

10. Automatic Licensing of Downstream Recipients.

Each time you convey a covered work, the recipient automatically receives a license from the original licensors, to run, modify and propagate that work, subject to this License. You are not responsible for enforcing compliance by third parties with this License.

An “entity transaction” is a transaction transferring control of an organization, or substantially all assets of one, or subdividing an organization, or merging organizations. If propagation of a covered work results from an entity transaction, each party to that transaction who receives a copy of the work also receives whatever licenses to the work the party’s predecessor in interest had or could give under the previous paragraph, plus a right to possession of the Corresponding Source of the work from the predecessor in interest, if the predecessor has it or can get it with reasonable efforts.

You may not impose any further restrictions on the exercise of the rights granted or affirmed under this License. For example, you may not impose a license fee, royalty, or other charge for exercise of rights granted under this License, and you may not initiate litigation (including a cross-claim or counterclaim in a lawsuit) alleging that any patent claim is infringed by making, using, selling, offering for sale, or importing the Program or any portion of it.

11. Patents.

A “contributor” is a copyright holder who authorizes use under this License of the Program or a work on which the Program is based. The work thus licensed is called the contributor’s “contributor version”.

A contributor’s “essential patent claims” are all patent claims owned or controlled by the contributor, whether already acquired or hereafter acquired, that would be infringed by some manner, permitted by this License, of making, using, or selling its contributor version, but do not include claims that would be infringed only as a consequence of further modification of the contributor version. For purposes of this definition, “control” includes the right to grant patent sublicenses in a manner consistent with the requirements of this License.

Each contributor grants you a non-exclusive, worldwide, royalty-free patent license under the contributor’s essential patent claims, to make, use, sell, offer for sale, import and otherwise run, modify and propagate the contents of its contributor version.

In the following three paragraphs, a “patent license” is any express agreement or commitment, however denominated, not to enforce a patent (such as an express permission to practice a patent or covenant not to sue for patent infringement). To “grant” such a patent license to a party means to make such an agreement or commitment not to enforce a patent against the party.

If you convey a covered work, knowingly relying on a patent license, and the Corresponding Source of the work is not available for anyone to copy, free of charge and under the terms of this License, through a publicly available network server or other readily accessible means, then you must either (1) cause the Corresponding Source to be so

available, or (2) arrange to deprive yourself of the benefit of the patent license for this particular work, or (3) arrange, in a manner consistent with the requirements of this License, to extend the patent license to downstream recipients. “Knowingly relying” means you have actual knowledge that, but for the patent license, your conveying the covered work in a country, or your recipient’s use of the covered work in a country, would infringe one or more identifiable patents in that country that you have reason to believe are valid.

If, pursuant to or in connection with a single transaction or arrangement, you convey, or propagate by procuring conveyance of, a covered work, and grant a patent license to some of the parties receiving the covered work authorizing them to use, propagate, modify or convey a specific copy of the covered work, then the patent license you grant is automatically extended to all recipients of the covered work and works based on it.

A patent license is “discriminatory” if it does not include within the scope of its coverage, prohibits the exercise of, or is conditioned on the non-exercise of one or more of the rights that are specifically granted under this License. You may not convey a covered work if you are a party to an arrangement with a third party that is in the business of distributing software, under which you make payment to the third party based on the extent of your activity of conveying the work, and under which the third party grants, to any of the parties who would receive the covered work from you, a discriminatory patent license (a) in connection with copies of the covered work conveyed by you (or copies made from those copies), or (b) primarily for and in connection with specific products or compilations that contain the covered work, unless you entered into that arrangement, or that patent license was granted, prior to 28 March 2007.

Nothing in this License shall be construed as excluding or limiting any implied license or other defenses to infringement that may otherwise be available to you under applicable patent law.

12. No Surrender of Others’ Freedom.

If conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot convey a covered work so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not convey it at all. For example, if you agree to terms that obligate you to collect a royalty for further conveying from those to whom you convey the Program, the only way you could satisfy both those terms and this License would be to refrain entirely from conveying the Program.

13. Use with the GNU Affero General Public License.

Notwithstanding any other provision of this License, you have permission to link or combine any covered work with a work licensed under version 3 of the GNU Affero General Public License into a single combined work, and to convey the resulting work. The terms of this License will continue to apply to the part which is the covered work, but the special requirements of the GNU Affero General Public License, section 13, concerning interaction through a network will apply to the combination as such.

14. Revised Versions of this License.

The Free Software Foundation may publish revised and/or new versions of the GNU General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Program specifies that a certain numbered version of the GNU General Public License “or any later version” applies to it, you have the option of following the terms and conditions either of that numbered version or of any later version published by the Free Software Foundation. If the Program does not specify a version number of the GNU General Public License, you may choose any version ever published by the Free Software Foundation.

If the Program specifies that a proxy can decide which future versions of the GNU General Public License can be used, that proxy’s public statement of acceptance of a version permanently authorizes you to choose that version for the Program.

Later license versions may give you additional or different permissions. However, no additional obligations are imposed on any author or copyright holder as a result of your choosing to follow a later version.

15. Disclaimer of Warranty.

THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

16. Limitation of Liability.

IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MODIFIES AND/OR CONVEYS THE PROGRAM AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE PROGRAM (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE PROGRAM TO OPERATE WITH ANY OTHER PROGRAMS), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

17. Interpretation of Sections 15 and 16.

If the disclaimer of warranty and limitation of liability provided above cannot be given local legal effect according to their terms, reviewing courts shall apply local law that most closely approximates an absolute waiver of all civil liability in connection with the Program, unless a warranty or assumption of liability accompanies a copy of the Program in return for a fee.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Programs

If you develop a new program, and you want it to be of the greatest possible use to the public, the best way to achieve this is to make it free software which everyone can redistribute and change under these terms.

To do so, attach the following notices to the program. It is safest to attach them to the start of each source file to most effectively state the exclusion of warranty; and each file should have at least the “copyright” line and a pointer to where the full notice is found.

one line to give the program's name and a brief idea of what it does.
Copyright (C) year name of author

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program. If not, see <https://www.gnu.org/licenses/>.

Also add information on how to contact you by electronic and paper mail.

If the program does terminal interaction, make it output a short notice like this when it starts in an interactive mode:

program Copyright (C) year name of author
This program comes with ABSOLUTELY NO WARRANTY; for details
type 'show w'. This is free software, and you are
welcome to redistribute it under certain conditions;
type 'show c' for details.

The hypothetical commands ‘show w’ and ‘show c’ should show the appropriate parts of the General Public License. Of course, your program’s commands might be different; for a GUI interface, you would use an “about box”.

You should also get your employer (if you work as a programmer) or school, if any, to sign a “copyright disclaimer” for the program, if necessary. For more information on this, and how to apply and follow the GNU GPL, see <https://www.gnu.org/licenses/>.

The GNU General Public License does not permit incorporating your program into proprietary programs. If your program is a subroutine library, you may consider it more useful to permit linking proprietary applications with the library. If this is what you want to do, use the GNU Lesser General Public License instead of this License. But first, please read <https://www.gnu.org/philosophy/why-not-lgpl.html>.

Contributors to GnuPG

The GnuPG project would like to thank its many contributors. Without them the project would not have been nearly as successful as it has been. Any omissions in this list are accidental. Feel free to contact the maintainer if you have been left out or some of your contributions are not listed.

David Shaw, Matthew Skala, Michael Roth, Niklas Hernaeus, Nils Ellmenreich, Rmi Guyomarch, Stefan Bellon, Timo Schulz and Werner Koch wrote the code. Birger Langkjer, Daniel Resare, Dokianakis Theofanis, Edmund GRIMLEY EVANS, Gal Quri, Gregory Steuck, Nagy Ferenc Lszl, Ivo Timmermans, Jacobo Tarri'o Barreiro, Janusz Aleksander Urbanowicz, Jedi Lin, Jouni Hiltunen, Laurentiu Buzdugan, Magda Procha'zkova', Michael Anckaert, Michal Majer, Marco d'Itri, Nilgun Belma Buguner, Pedro Morais, Tedi Heriyanto, Thiago Jung Bauermann, Rafael Caetano dos Santos, Toomas Soome, Urko Lusa, Walter Koch, Yosiaki IIDA did the official translations. Mike Ashley wrote and maintains the GNU Privacy Handbook. David Scribner is the current FAQ editor. Lorenzo Cappelletti maintains the web site.

The new modularized architecture of gnupg 1.9 as well as the X.509/CMS part has been developed as part of the gypten project. Direct contributors to this project are: Bernhard Herzog, who did extensive testing and tracked down a lot of bugs. Bernhard Reiter, who made sure that we met the specifications and the deadlines. He did extensive testing and came up with a lot of suggestions. Jan-Oliver Wagner made sure that we met the specifications and the deadlines. He also did extensive testing and came up with a lot of suggestions. Karl-Heinz Zimmer and Marc Mutz had to struggle with all the bugs and misconceptions while working on KDE integration. Marcus Brinkman extended GPGME, cleaned up the Assuan code and fixed bugs all over the place. Moritz Schulte took over Libgcrypt maintenance and developed it into a stable and useful library. Steffen Hansen had a hard time to write the dirmngr due to underspecified interfaces. Thomas Koester did extensive testing and tracked down a lot of bugs. Werner Koch designed the system and wrote most of the code.

The following people helped greatly by suggesting improvements, testing, fixing bugs, providing resources and doing other important tasks: Adam Mitchell, Albert Chin, Alec Habig, Allan Clark, Anand Kumria, Andreas Haumer, Anthony Mulcahy, Ariel T Glenn, Bob Mathews, Bodo Moeller, Brendan O'Dea, Brenno de Winter, Brian M. Carlson, Brian Moore, Brian Warner, Bryan Fullerton, Caskey L. Dickson, Cees van de Griend, Charles Levert, Chip Salzenberg, Chris Adams, Christian Biere, Christian Kurz, Christian von Roques, Christopher Oliver, Christian Recktenwald, Dan Winship, Daniel Eisenbud, Daniel Koenig, Dave Dykstra, David C Niemi, David Champion, David Ellement, David Hallinan, David Hollenberg, David Mathog, David R. Bergstein, Detlef Lannert, Dimitri, Dirk Lattermann, Dirk Meyer, Disastry, Douglas Calvert, Ed Boraas, Edmund GRIMLEY EVANS, Edwin Woudt, Enzo Michelangeli, Ernst Molitor, Fabio Coatti, Felix von Leitner, fish stiqz, Florian Weimer, Francesco Potorti, Frank Donahoe, Frank Heckenbach, Frank Stajano, Frank Tobin, Gabriel Rosenkoetter, Gal Quri, Gene Carter, Geoff Keating, Georg Schwarz, Giampaolo Tomassoni, Gilbert Fernandes, Greg Louis, Greg Troxel, Gregory Steuck, Gregory Barton, Harald Denker, Holger Baust, Hendrik Buschkamp, Holger Schurig, Holger Smolinski, Holger Trapp, Hugh Daniel, Huy Le, Ian McKellar, Ivo Timmermans, Jan Krueger, Jan Niehusmann, Janusz A. Urbanowicz, James Troup, Jean-loup Gailly, Jeff

Long, Jeffery Von Ronne, Jens Bachem, Jeroen C. van Gelderen, J Horacio MG, J. Michael Ashley, Jim Bauer, Jim Small, Joachim Backes, Joe Rhett, John A. Martin, Johnny Teveen, Jrg Schilling, Jos Backus, Joseph Walton, Juan F. Codagnone, Jun Kuriyama, Kahil D. Jallad, Karl Fogel, Karsten Thygesen, Katsuhiko Kondou, Kazu Yamamoto, Keith Clayton, Kevin Ryde, Klaus Singvogel, Kurt Garloff, Lars Kellogg-Stedman, L. Sassaman, M Taylor, Marcel Waldvogel, Marco d'Itri, Marco Parrone, Marcus Brinkmann, Mark Adler, Mark Elbrecht, Mark Pettit, Markus Friedl, Martin Kahlert, Martin Hamilton, Martin Schulte, Matt Kraai, Matthew Skala, Matthew Wilcox, Matthias Urlichs, Max Valianskiy, Michael Engels, Michael Fischer v. Mollard, Michael Roth, Michael Sobolev, Michael Tokarev, Nicolas Graner, Mike McEwan, Neal H Walfield, Nelson H. F. Beebe, NIIBE Yutaka, Niklas Hernaeus, Nimrod Zimerman, N J Doye, Oliver Haakert, Oskari Jskelinen, Pascal Scheffers, Paul D. Smith, Per Cederqvist, Phil Blundell, Philippe Laliberte, Peter Fales, Peter Gutmann, Peter Marschall, Peter Valchev, Piotr Krukowiecki, QingLong, Ralph Gillen, Rat, Reinhard Wobst, Rmi Guyomarch, Reuben Sumner, Richard Outerbridge, Robert Joop, Roddy Strachan, Roger Sondermann, Roland Rosenfeld, Roman Pavlik, Ross Golder, Ryan Malayter, Sam Roberts, Sami Tolvanen, Sean MacLennan, Sebastian Klemke, Serge Munhoven, SL Baur, Stefan Bellon, Dr.Stefan.Dalibor, Stefan Karrmann, Stefan Keller, Steffen Ullrich, Steffen Zahn, Steven Bakker, Steven Murdoch, Susanne Schultz, Ted Cabeen, Thiago Jung Bauermann, Thijmen Klok, Thomas Roessler, Tim Mooney, Timo Schulz, Todd Vierling, TOGAWA Satoshi, Tom Spindler, Tom Zerucha, Tomas Fasth, Tommi Komulainen, Thomas Klausner, Tomasz Kozlowski, Thomas Mikkelsen, Ulf Mller, Urko Lusa, Vincent P. Broman, Volker Quetschke, W Lewis, Walter Hofmann, Walter Koch, Wayne Chapeskie, Wim Vandeputte, Winona Brown, Yosiaki IIDA, Yoshihiro Kajiki and Gerlinde Klaes.

This software has been made possible by the previous work of Chris Wedgwood, Jean-loup Gailly, Jon Callas, Mark Adler, Martin Hellman, Paul Kendall, Philip R. Zimmermann, Peter Gutmann, Philip A. Nelson, Taher Elgamal, Torbjorn Granlund, Whitfield Diffie, some unknown NSA mathematicians and all the folks who have worked hard to create complete and free operating systems.

And finally we'd like to thank everyone who uses these tools, submits bug reports and generally reminds us why we're doing this work in the first place.

Glossary

- ‘ARL’ The *Authority Revocation List* is technical identical to a CRL but used for CAs and not for end user certificates.
- ‘Chain model’ Verification model for X.509 which uses the creation date of a signature as the date the validation starts and in turn checks that each certificate has been issued within the time frame, the issuing certificate was valid. This allows the verification of signatures after the CA’s certificate expired. The validation test also required an online check of the certificate status. The chain model is required by the German signature law. See also *Shell model*.
- ‘CMS’ The *Cryptographic Message Standard* describes a message format for encryption and digital signing. It is closely related to the X.509 certificate format. CMS was formerly known under the name PKCS#7 and is described by RFC3369.
- ‘CRL’ The *Certificate Revocation List* is a list containing certificates revoked by the issuer.
- ‘CSR’ The *Certificate Signing Request* is a message send to a CA to ask them to issue a new certificate. The data format of such a signing request is called PKCS#10.
- ‘OpenPGP’ A data format used to build a PKI and to exchange encrypted or signed messages. In contrast to X.509, OpenPGP also includes the message format but does not explicitly demand a specific PKI. However any kind of PKI may be build upon the OpenPGP protocol.
- ‘Keygrip’ This term is used by GnuPG to describe a 20 byte hash value used to identify a certain key without referencing to a concrete protocol. It is used internally to access a private key. Usually it is shown and entered as a 40 character hexadecimal formatted string.
- ‘OCSP’ The *Online Certificate Status Protocol* is used as an alternative to a CRL. It is described in RFC 2560.
- ‘PSE’ The *Personal Security Environment* describes a database to store private keys. This is either a smartcard or a collection of files on a disk; the latter is often called a Soft-PSE.
- ‘Shell model’ The standard model for validation of certificates under X.509. At the time of the verification all certificates must be valid and not expired. See also *Chain model*.
- ‘X.509’ Description of a PKI used with CMS. It is for example defined by RFC3280.

Option Index

A

add-servers 28
 agent-program..... 62, 101, 152
 allow-admin 122
 allow-emacs-pinentry 7
 allow-freeform-uid 80
 allow-loopback-pinentry..... 6
 allow-multiple-messages..... 83
 allow-non-selfsigned-uid 80
 allow-ocsp..... 28
 allow-preset-passphrase..... 6
 allow-secret-key-import..... 83
 allow-version-check..... 26
 allow-weak-digest-algos..... 81
 allow-weak-key-signatures 81
 always-trust 84
 armor..... 66, 103
 ask-cert-expire..... 83
 ask-cert-level..... 56
 ask-sig-expire..... 83
 assume-armor..... 103
 assume-base64..... 103
 assume-binary..... 103
 attribute-fd 76
 attribute-file..... 76
 auto-check-trustdb 62
 auto-expand-secmem 11
 auto-issuer-key-retrieve 102
 auto-key-import..... 59
 auto-key-locate..... 58
 auto-key-retrieve..... 59

B

base64..... 103
 batch..... 4, 51
 bzip2-compress-level 55
 bzip2-decompress-lowmem..... 55

C

c..... 25
 cache-cert 157
 call-dirmngr 97
 call-protect-tool..... 98
 card-edit..... 39
 card-status 39
 card-timeout..... 122
 cert-digest-algo..... 78
 cert-notation..... 76
 cert-policy-url..... 77
 change-passphrase..... 50, 100
 change-pin..... 39
 check-passphrase-pattern..... 8

check-signatures..... 38
 check-sigs..... 38
 check-trustdb..... 41
 cipher-algo..... 77, 104
 clear-sign..... 36
 clearsign..... 36
 cms 160
 command-fd..... 80
 command-file..... 80
 comment..... 76
 compliance..... 74
 compliant-needed..... 61
 compress-algo..... 78
 compress-level..... 55
 connect-quick-timeout..... 26
 connect-timeout..... 26
 create..... 159
 create-socketdir..... 140
 csh..... 6, 25
 ctapi-driver..... 122

D

daemon..... 3, 23, 119
 dearmor..... 42
 debug..... 5, 25, 75, 105, 120
 debug-all..... 5, 25, 75, 105, 121
 debug-allow-core-dump..... 106, 121
 debug-assuan-log-cats..... 121
 debug-disable-ticker..... 121
 debug-ignore-expiration 106
 debug-iolbf 75
 debug-level..... 5, 24, 74, 105, 120
 debug-log-tid 121
 debug-no-chain-validation 106
 debug-pinentry 6
 debug-quick-random 6
 debug-wait 5, 25, 121
 decode..... 152
 decrypt..... 36, 97, 159
 decrypt-files 37
 default-cache-ttl..... 7
 default-cert-expire 83
 default-cert-level 56
 default-key..... 50, 103
 default-keyserver-url..... 84
 default-new-key-algo *string* 83
 default-preference-list..... 84
 default-recipient..... 50
 default-recipient-self..... 50
 default-sig-expire 83
 delete-keys..... 39, 99
 delete-secret-and-public-key..... 39
 delete-secret-keys 39

deny-admin	122
desig-revoke	45
detach-sign	36
digest-algo	78
directory	160, 162, 163
dirmngr	152
dirmngr-program	62, 101, 152
disable-application	123
disable-ccid	122
disable-check-own-socket	9, 25
disable-cipher-algo	78
disable-crl-checks	101
disable-dsa2	53
disable-extended-key-format	10
disable-http	27
disable-ipv4	27
disable-ipv6	27
disable-large-rsa	53
disable-ldap	27
disable-mdc	72
disable-ocsp	102
disable-pinpad	122
disable-policy-checks	101
disable-pubkey-algo	78
disable-scdaemon	9
disable-signer-uid	72
disable-trusted-cert-crl-check	101
display	9
display-charset	55
display-charset:iso-8859-1	55
display-charset:iso-8859-15	55
display-charset:iso-8859-2	55
display-charset:koi8-r	55
display-charset:utf-8	55
dry-run	74, 159
dump-cert	98
dump-chain	98
dump-external-keys	99
dump-keys	98
dump-options	3, 23, 35, 97, 119
dump-secret-keys	98

E

edit-card	39
edit-key	45
emit-version	76
enable-crl-checks	101
enable-dsa2	53
enable-extended-key-format	10
enable-issuer-based-crl-check	102
enable-large-rsa	53
enable-ocsp	102
enable-passphrase-history	8
enable-pinpad-varlen	122
enable-policy-checks	101
enable-progress-filter	75
enable-putty-support	10

enable-special-filenames	83, 137
enable-ssh-support	10
enable-trusted-cert-crl-check	101
enarmor	42
encrypt	36, 97, 159
encrypt-files	37
encrypt-to	64
enforce-passphrase-constraints	7
escape-from-lines	79
exec	152
exec-path	54
exit-on-status-write-error	63
expert	64
export	39, 99
export-filter	68
export-options	69
export-ownertrust	41
export-secret-key-p12	99
export-secret-key-p8	99
export-secret-key-raw	99
export-secret-keys	40
export-secret-subkeys	40
export-ssh-key	40
extra-digest-algo	104
extra-socket	9
extract	159

F

faked-system-time	5, 75, 104
fast-list-mode	82
fetch-crl	23
fetch-keys	41
fingerprint	38
fixed-list-mode	70
flush	24
for-your-eyes-only	77
force	25, 135
force-crl-refresh	102
force-default-responder	157
force-mdc	72
forget	151
from	163
full-gen-key	44
full-generate-key	44

G

gen-key	44, 98
gen-prime	42
gen-random	42
gen-revoke	44
generate-designated-revocation	45
generate-key	44, 98
generate-revocation	44
gnupg	73
gpg	160
gpg-agent-info	62

gpg-args 160
 gpgconf-list 84
 gpgconf-test 84
 grab 6
 group 65

H

header 163
 help 3, 23, 35, 97, 119, 135, 156, 160, 162, 164
 hex 152
 hidden-encrypt-to 64
 hidden-recipient 64
 hidden-recipient-file 64
 homedir 4, 54, 100, 119, 137, 140, 151, 158
 honor-http-proxy 27
 http-proxy 27

I

ignore-cache-for-signing 7
 ignore-cert-extension 29, 102
 ignore-crc-error 81
 ignore-http-dp 27
 ignore-ldap-dp 27
 ignore-mdc-error 81
 ignore-ocsp-service-url 27
 ignore-time-conflict 80, 136
 ignore-valid-from 80
 import 40, 99
 import-filter 68
 import-options 66
 import-ownertrust 41
 include-certs 104
 include-key-block 72
 input-size-hint 66
 interactive 74

K

keep-display 9
 keep-tty 9
 key-origin 66
 keydb-clear-some-cert-flags 99
 keyedit:addcardkey 47
 keyedit:addkey 47
 keyedit:addphoto 46
 keyedit:addrvoker 48
 keyedit:adduid 45
 keyedit:bkuptocard 47
 keyedit:change-usage 48
 keyedit:check 45
 keyedit:clean 48
 keyedit:cross-certify 48
 keyedit:delkey 47
 keyedit:delsig 45
 keyedit:deluid 46
 keyedit:disable 48

keyedit:enable 48
 keyedit:expire 47
 keyedit:key 45
 keyedit:keyserver 46
 keyedit:keytocard 47
 keyedit:lsign 45
 keyedit:minimize 48
 keyedit:notation 46
 keyedit:nrsign 45
 keyedit:passwd 48
 keyedit:pref 46
 keyedit:primary 46
 keyedit:quit 48
 keyedit:revkey 47
 keyedit:revsig 45
 keyedit:revuid 46
 keyedit:save 48
 keyedit:setpref 46
 keyedit:showphoto 46
 keyedit:showpref 46
 keyedit:sign 45
 keyedit:toggle 48
 keyedit:trust 47
 keyedit:tsign 45
 keyedit:uid 45
 keyid-format 60
 keyring 54, 136
 keyserver 26, 60
 keyserver-options 60
 kill 140
 known-notation 77

L

launch 140
 lc-ctype 9
 lc-messages 9
 ldap-proxy 27
 ldapserverlist-file 28
 ldaptimeout 28
 learn-card 100
 legacy-list-mode 71
 limit-card-insert-tries 63
 list-archive 159
 list-chain 98
 list-config 84
 list-crls 23
 list-gcrypt-config 84
 list-keys 37, 98
 list-only 74
 list-options 51
 list-options:show-keyring 52
 list-options:show-keyserver-urls 52
 list-options:show-notations 51
 list-options:show-only-fpr-mbox 52
 list-options:show-photos 51
 list-options:show-policy-urls 51
 list-options:show-sig-expire 52

list-options:show-sig-subpackets	52
list-options:show-std-notations	51
list-options:show-uid-validity	52
list-options:show-unusable-subkeys	52
list-options:show-unusable-uids	52
list-options:show-usage	51
list-options:show-user-notations	51
list-packets	39
list-secret-keys	37, 98
list-signatures	82
list-sigs	82
listen-backlog	9, 26, 121
load-crl	23, 157
local-user	65, 103, 159
locate-external-keys	38
locate-keys	38
lock-multiple	62
lock-never	63
lock-once	62
log-file	6, 24, 75, 101, 121, 136, 158
logger-fd	75, 136
lookup	157
lsign-key	49

M

mangle-dos-filenames	56
marginals-needed	61
max-cache-ttl	7
max-cache-ttl-ssh	7
max-cert-depth	62
max-output	66
max-passphrase-days	8
max-replies	29
min-cert-level	56
min-passphrase-len	7
min-passphrase-nonalpha	8
multi-server	119
multifile	37

N

nameserver	27
no	51
no-allow-external-cache	7
no-allow-loopback-pinentry	6
no-allow-mark-trusted	6
no-armor	66
no-auto-key-import	59
no-auto-key-retrieve	59
no-autostart	62, 101, 152
no-batch	51
no-common-certs-import	106
no-default-keyring	81
no-default-recipient	50
no-detach	6, 121
no-encrypt-to	65
no-expensive-trust-checks	84

no-ext-connect	152
no-grab	6
no-greeting	63
no-groups	65
no-keyring	81
no-literal	82
no-mangle-dos-filenames	56
no-options	55
no-random-seed-file	63
no-secmem-warning	63, 101
no-sig-cache	62
no-skip-hidden-recipients	66
no-symkey-cache	80
no-tty	51
no-use-standard-socket	9
no-use-tor	25
no-verbose	50
not-dash-escaped	79
null	160

O

ocsp	156
ocsp-current-period	29
ocsp-max-clock-skew	29
ocsp-max-period	29
ocsp-responder	28
ocsp-signer	29
only-ldap-proxy	28
openpgp	73, 160
options	4, 24, 55, 100, 119
output	66, 103, 136, 159, 162, 163
override-session-key	82

P

p12-charset	103
passphrase	79, 151
passphrase-fd	79, 106
passphrase-file	79
passphrase-repeat	79
passwd	50, 100
pcsc-driver	121
pem	156
permission-warning	63
personal-cipher-preferences	72
personal-compress-preferences	72
personal-digest-preferences	72
pgp6	74
pgp7	74
pgp8	74
photo-viewer	53
pinentry-invisible-char	8
pinentry-mode	80, 106
pinentry-program	8
pinentry-timeout	8
pinentry-touch-file	8
ping	157

policy-file 100
 prefer-system-dirmngr 101
 preserve-permissions 84
 preset 150
 primary-keyring 54
 print-md 42

Q

q 151, 158
 quick-add-key 43
 quick-add-uid 49
 quick-gen-key 42
 quick-generate-key 42
 quick-lsign-key 49
 quick-revoke-sig 49
 quick-revoke-uid 49
 quick-set-expire 43
 quick-set-primary-uid 49
 quick-sign-key 49
 quiet 4, 51, 136, 140, 151, 156, 158, 159, 162, 164

R

raw-socket 152
 reader-port 122
 rebuild-keydb-caches 42
 receive-keys 40
 recipient 64, 103, 159
 recipient-file 64
 recursive-resolver 25
 recv-keys 40
 refresh-keys 41
 reload 139
 remove-socketdir 140
 request-origin 80, 106
 require-cross-certification 64
 require-secmem 63
 resolver-timeout 26
 rfc2440 74
 rfc4880 73
 rfc4880bis 73
 run 152

S

s 25
 s2k-calibration 11
 s2k-cipher-algo 73
 s2k-count 11, 73
 s2k-digest-algo 73
 s2k-mode 73
 scdaemon-program 9
 search-keys 41
 secret-keyring 54
 send 161, 163
 send-keys 40

sender 65
 server 3, 23, 97, 119
 set-filename 77, 160
 set-filesize 82
 set-notation 76
 set-policy-url 77
 sh 6, 25
 show-keyring 84
 show-keys 38
 show-notation 85
 show-photos 84
 show-policy-url 85
 show-session-key 82
 shutdown 24
 sig-keyserver-url 77
 sig-notation 76
 sig-policy-url 77
 sign 35, 97
 sign-key 49
 skip-crypto 159
 skip-hidden-recipients 66
 skip-verify 81
 squid-mode 157
 ssh-fingerprint-digest 11
 standard-resolver 25
 status-fd 75, 136, 141, 162
 status-file 75
 store 36
 subst 152
 supervised 4, 23
 symmetric 36

T

tar-args 160
 textmode 71
 throw-keyids 78
 time-only 135
 tls-debug 25
 tofu-default-policy 62
 tofu-policy 42
 trust-model 56
 trust-model:always 58
 trust-model:auto 58
 trust-model:classic 57
 trust-model:direct 58
 trust-model:pgp 57
 trust-model:tofu 57
 trust-model:tofu+pgp 58
 trustdb-name 54
 trusted-key 56
 try-all-secrets 65
 try-secret-key 65
 ttyname 9
 ttytype 9

U

ungroup.....	65
update-trustdb.....	41
url.....	157
use-agent.....	62
use-embedded-filename.....	77
use-standard-socket.....	9
use-standard-socket-p.....	9
use-tor.....	25
utf8-strings.....	55, 160

V

v.....	24, 100, 120, 156
validate.....	157
validation-model.....	102
verbose....	4, 24, 50, 100, 120, 135, 136, 151, 156, 158, 159, 162, 164
verify.....	36, 97
verify-files.....	37
verify-options.....	52
verify-options: pka-lookups.....	53
verify-options: pka-trust-increase.....	53
verify-options: show-keyserver-urls.....	52
verify-options: show-notations.....	52
verify-options: show-photos.....	52
verify-options: show-policy-urls.....	52
verify-options: show-primary-uid-only.....	53
verify-options: show-std-notations.....	52
verify-options: show-uid-validity.....	53

verify-options: show-unusable-uids.....	53
verify-options: show-user-notations.....	52
version.....	3, 23, 35, 97, 119, 135, 156, 160, 162, 164

W

warranty.....	35, 97
weak-digest.....	81, 137
with-colons.....	70, 162
with-dir.....	164
with-ephemeral-keys.....	105
with-file.....	164
with-fingerprint.....	71
with-icao-spelling.....	71
with-key-data.....	82, 103
with-key-origin.....	71
with-keygrip.....	71
with-secret.....	71, 104
with-subkey-fingerprint.....	71
with-validation.....	103
with-wkd-hash.....	71

X

xauthority.....	9
-----------------	---

Y

yes.....	51
----------	----

Environment Variable and File Index

•	LC_CTYPE..... 116
.gpg-v21-migrated..... 86	LC_MESSAGES..... 116
~	LINES..... 87
~/gnupg..... 85	
A	O
ASSUAN_DEBUG..... 121	openpgp-revocs.d..... 86
C	P
COLUMNS..... 87	PATH..... 54
com-certs.pem..... 108	PINENTRY_USER_DATA..... 87, 116
	policies.txt..... 107
	private-keys-v1.d..... 13
	pubring.gpg..... 85
	pubring.kbx..... 86, 108
D	Q
dirmngr.conf..... 30	qualified.txt..... 107
DISPLAY..... 115	
G	R
GNUPGHOME.. 4, 54, 87, 100, 119, 137, 140, 151, 158	random_seed..... 86, 108
gpg-agent.conf..... 11	
gpg.conf..... 85	S
GPG_TTY..... 3, 115	S.gpg-agent..... 108
gpgconf.ct1... 4, 54, 100, 119, 137, 140, 151, 158	secring.gpg..... 86
gpgsm.conf..... 107	SHELL..... 6
H	sshcontrol..... 12
help.txt..... 107	
HKCU\Software\GNU\GnuPG:DefaultLogFile.... 6	T
HKCU\Software\GNU\GnuPG:HomeDir.... 4, 54, 100, 119, 137, 140, 151, 158	TERM..... 116
HOME..... 86	trustdb.gpg..... 86
http_proxy..... 27	trustlist.txt..... 11
L	X
LANGUAGE..... 87	XAUTHORITY..... 116

Index

C

command options 3, 23, 35, 97, 119
contributors 193

D

DIRMNGR command options 23

G

GPG command options 35
GPG-AGENT command options 3
gpgconf.conf 150
GPGSM command options 97

O

options, DIRMNGR command 23
options, GPG command 35
options, GPG-AGENT command 3
options, GPGSM command 97

options, SCDAEMON command 119

R

relax 12

S

scd-event 124
scdaemon.conf 124
SCDAEMON command options 119
SIGHUP 13, 31
SIGINT 13, 31
SIGTERM 13, 31
SIGUSR1 13, 31
SIGUSR2 13
swdb.lst 150

T

trust values 133

